

Autodesk®
Smoke® 2011 Extension 1

A Discreet® Systems product

For Mac OS® X

Installation and
Licensing Guide



Autodesk® Visual Effects and Finishing 2011

© 2010 Autodesk, Inc. All rights reserved. Except as otherwise permitted by Autodesk, Inc., this publication, or parts thereof, may not be reproduced in any form, by any method, for any purpose.

Certain materials included in this publication are reprinted with the permission of the copyright holder.

Portions relating to MD5 Copyright © 1991-2, RSA Data Security, Inc. Created 1991. All rights reserved. License to copy and use this software is granted provided that it is identified as the "RSA Data Security, Inc. MD5 Message-Digest Algorithm" in all material mentioning or referencing this software or this function. License is also granted to make and use derivative works provided that such works are identified as "derived from the RSA Data Security, Inc. MD5 Message-Digest Algorithm" in all material mentioning or referencing the derived work. RSA Data Security, Inc. makes no representations concerning either the merchantability of this software or the suitability of this software for any particular purpose. It is provided "as is" without express or implied warranty of any kind. These notices must be retained in any copies of any part of this documentation and/or software.

Trademarks

The following are registered trademarks or trademarks of Autodesk, Inc., and/or its subsidiaries and/or affiliates in the USA and other countries: 3DEC (design/logo), 3December, 3December.com, 3ds Max, Algor, Alias, Alias (swirl design/logo), AliasStudio, AliasWavefront (design/logo), ATC, AUGI, AutoCAD, AutoCAD Learning Assistance, AutoCAD LT, AutoCAD Simulator, AutoCAD SQL Extension, AutoCAD SQL Interface, Autodesk, Autodesk Envision, Autodesk Intent, Autodesk Inventor, Autodesk Map, Autodesk MapGuide, Autodesk Streamline, AutoLISP, AutoSnap, AutoSketch, AutoTrack, Backburner, Backdraft, Built with ObjectARX (logo), Burn, Buzzsaw, CAiCE, Civil 3D, Cleaner, Cleaner Central, ClearScale, Colour Warper, Combustion, Communication Specification, Constructware, Content Explorer, Dancing Baby (image), DesignCenter, Design Doctor, Designer's Toolkit, DesignKids, DesignProf, DesignServer, DesignStudio, Design Web Format, Discreet, DWF, DWG, DWG (logo), DWG Extreme, DWG TrueConvert, DWG TrueView, DXF, Ecotect, Exposure, Extending the Design Team, Face Robot, FBX, Fempro, Fire, Flame, Flare, Flint, FMDesktop, Freewheel, GDX Driver, Green Building Studio, Heads-up Design, Heidi, HumanIK, IDEA Server, i-drop, ImageModeler, iMOUT, Incinerator, Inferno, Inventor, Inventor LT, Kaydara, Kaydara (design/logo), Kynapse, Kynogon, LandXplorer, Lustre, MatchMover, Maya, Mechanical Desktop, Moldflow, Moonbox, MotionBuilder, Movimento, MPA, MPA (design/logo), Moldflow Plastics Advisers, MPI, Moldflow Plastics Insight, MPX, MPX (design/logo), Moldflow Plastics Xpert, Mudbox, Multi-Master Editing, Navisworks, ObjectARX, ObjectDBX, Open Reality, Opticore, Opticore Opus, Pipeplus, PolarSnap, PortfolioWall, Powered with Autodesk Technology, Productstream, ProjectPoint, ProMaterials, RasterDWG, RealDWG, Real-time Roto, Recognize, Render Queue, Retimer, Reveal, Revit, Showcase, ShowMotion, SketchBook, Smoke, Softimage, SoftimageXSI (design/logo), Sparks, SteeringWheels, Stitcher, Stone, StudioTools, ToolClip, Topobase, Toxik, TrustedDWG, ViewCube, Visual, Visual LISP, Volo, Vtour, Wire, Wiretap, WiretapCentral, XSI, and XSI (design/logo).

Adobe, Flash and Reader are either trademarks or registered trademarks of Adobe Systems Incorporated in the United States and/or countries.

Automatic Duck and the duck logo are trademarks of Automatic Duck, Inc.

FFmpeg is a trademark of Fabrice Bellard, originator of the FFmpeg project.

Python is a registered trademark of Python Software Foundation.

All other brand names, product names or trademarks belong to their respective holders.

Disclaimer

THIS PUBLICATION AND THE INFORMATION CONTAINED HEREIN IS MADE AVAILABLE BY AUTODESK, INC. "AS IS." AUTODESK, INC. DISCLAIMS ALL WARRANTIES, EITHER EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE REGARDING THESE MATERIALS.

Published by: Autodesk, Inc.
111 McInnis Parkway
San Rafael, CA 94903, USA

Title: Autodesk Smoke 2011 Extension 1 for Mac OS X Installation and Licensing Guide
Document Version: 1
Date: September 27, 2010

Contents

Chapter 1	Introduction	1
	About this Guide	1
	Notation Conventions	1
	Related Documentation	2
	Contacting Customer Support	2
Chapter 2	Preparing Your Workstation	3
	Preparing Your Hardware	3
	Preparing Your Media Storage	3
	Recommended File System	4
	Updating Your Operating System	4
	Installing or Updating Hardware Drivers	4
	Setting System Preferences	4
	Configuring Your Network	5
	Configuring Mac OS X Keyboard Shortcuts	5
	Configuring Wacom Pen Buttons	6
Chapter 3	Installing and Licensing Smoke	9
	About Trial License Installation	9
	Installing the Trial Version Smoke	9
	Converting from Trial to a Network License	12
	About Installing Smoke with the Network License Server	12
	Do not use the Activate button, unless you have a Student edition	13
	Installing Smoke with a Local Network License Server	13
	Get Your License Server Hostname and Server ID Manually	19
	About Standalone License Installation	20
	Installing and Activating the Student Edition of Smoke	20
	Offline Registration and Activation	24
	Uninstalling Smoke	25
	Other Software	26
	Installing and Licensing Wiretap Gateway	26
	Installing and Licensing Autodesk Burn	27
Chapter 4	Configuring Smoke	29
	About Smoke Setup	29
	Configuring General Settings	29
	Defining the Video Preview Device	31
	Defining VTRs	32
	Configuring VTR Emulation	32
	Adding or Editing Media Storage Volumes	33
	Configuring Backburner Settings	34
	Configuring the License Server	36
	About Compatibility with Projects Created in Previous Versions of Smoke	36
	Upgrading Smoke Projects to the Current Version	37
	Transferring Clip Libraries from a Previous Project on a Remote Host to a 2011 Extension 1 Project	38

Chapter 5	Troubleshooting Smoke Installation, Licensing and Configuration	39
	Invalid Serial Number Error	39
	Troubleshooting License Errors	40
	Verifying the License Server	40
	Licensing Errors Caused by DHCP Problems	41
	Restarting the License Server	41
	Verifying the License File	42
	Enabling Remote Login	43
	Viewing Application Error Messages	44
	Checking that Background Services are Running	44
	Forcing Smoke to Exit	45
	Handling System Freezes	46
	Repairing Media Storage Mount Points	46
	Fixing VOLUMEMGT and No Volume Errors	47
	Rebooting after an IP Address or Host Name Change	47
	Sending Application Logs to Autodesk Customer Support	47
	Switching Your Mac OS X Kernel between 32-bit Mode and 64-bit Mode	48
	Appendix: Autodesk Licensing	49
Appendix A	Network Licensing	51
	Introduction	51
	Plan Your Network Licensing	51
	System Requirements for the Network License Manager (Windows)	51
	System Requirements for the Network License Manager (Mac OS X)	53
	System Requirements for the Network License Manager (Linux)	53
	Plan Your License Server Configuration	54
	Learn About Your License	55
	Network License Manager	60
	Install the Network License Manager	60
	Install the Network License Manager (Mac OS X)	60
	Install the Network License Manager (Linux)	61
	Obtain a License Through autodesk.com	61
	Obtain the Server Host Name and Host ID Manually	61
	Creating Your License File (Linux)	62
	Uninstall the Network License Manager	62
	Network Licensing Tools	63
	FLEXnet Configuration Tools	63
	License Borrowing	64
	Overview	64
	Borrow a License	65
	BORROWLICENSE Command	66
	Return a License	66
	RETURNLICENSE Command	67
Appendix B	Stand-Alone Licensing	69
	Introduction	69
	Multi-Seat Stand-Alone License	70
	Activate Your Product	70
	Register Your Product	70
	Manage Your Stand-Alone License	70
	Check Product Information	70
	View Product Information	71
	Save License Information as a Text File	71
	Update Your Serial Number	71
	Transfer Your Stand-Alone License	72
	About the Licence Transfer Utility	72
	Install the Autodesk Product	72
	Export a License	72

Import a License	72
Troubleshoot a Stand-Alone License Error	72
Hardware Changes	72
Reinstalling an Operating System	73
Changing the System Date and Time	73
Distributing Software Image to Multiple Computers	73
Preserving Licenses on Re-Imaged Computers	73
Appendix C Licensing Glossary	75
Glossary	75
Index	77

Introduction

1

Topics in this chapter:

- [About this Guide](#) on page 1
- [Notation Conventions](#) on page 1
- [Related Documentation](#) on page 2
- [Contacting Customer Support](#) on page 2

About this Guide

This guide contains detailed information about installing and licensing Autodesk® Smoke® 2011 Extension 1 for Mac OS® X. The document also contains general guidelines about preparing your workstation and operating system before you install the Smoke software.

This document assumes that you have regular user knowledge of Apple® workstations and Mac OS X. You do not need prior knowledge of Autodesk Visual Effects and Finishing software.

Notation Conventions

A number of style conventions are used throughout your documentation. These conventions and examples of their use are shown as follows.

Convention	Example
Text that you enter in a command line or shell appears in Courier bold. Press the Enter key after each command.	install rpm -qa
Variable names appear in Courier, enclosed in angle brackets.	<filename>

Convention	Example
Feedback from the command line or shell appears in Courier.	<code>limit coredumpsize</code>
Directory names, filenames, URLs, and command line utilities appear in italics.	<i>/usr/discreet</i>

Related Documentation

Documentation for this release is installed with the product as PDF files and as an HTML help system, and is also available on the Autodesk web site at <http://www.autodesk.com/me-documentation>. From this page you can access the complete documentation library.

You should also refer to the product release notes for all late-breaking release information.

Contacting Customer Support

You can obtain support for Smoke on the Mac by making a Service Request at the Autodesk Subscription Center (registration required).

Go to <http://www.autodesk.com/subscriptionlogin>. Once logged into your account at the Subscription Center, select "Support Requests".

Customer support is also available through your Autodesk reseller. To find a reseller near you, consult thereseller look-up database at <http://www.autodesk.com/resellers>.

Before contacting Autodesk Customer Support, run the *platforminfo* command-line utility to gather important information on your system.

To obtain system information:

- 1 Open the Terminal from the *Applications / Utilities* folder.

- 2 Type the following command:

```
platforminfo
```

The output looks similar to the following:

```
Workstation: MacPro4,1
```

```
CPU: 2 Quad-Core Intel Xeon @ 2.93 GHz, 8 cores
```

```
RAM: 12 GB of RAM
```

```
Graphics: NVIDIA Quadro FX 4800 Driver: 19.5.2f10
```

```
OS: Mac OS X 10.6.3 (10D561)
```

```
Kernel: Darwin 10.3.0
```

- 3 Send this information to Autodesk Customer Support.

Preparing Your Workstation

2

Topics in this chapter:

- [Preparing Your Hardware](#) on page 3
- [Preparing Your Media Storage](#) on page 3
- [Updating Your Operating System](#) on page 4
- [Installing or Updating Hardware Drivers](#) on page 4
- [Setting System Preferences](#) on page 4
- [Configuring Your Network](#) on page 5
- [Configuring Mac OS X Keyboard Shortcuts](#) on page 5
- [Configuring Wacom Pen Buttons](#) on page 6

Preparing Your Hardware

Before you set up your workstation, consult the Autodesk Smoke for Mac OS X System Requirements Web page at www.autodesk.com/smoke-systemrequirements, and make sure your hardware meets the minimum requirements for your version of Smoke for Mac OS X.

Consult your hardware documentation for information on how to install the necessary add-on cards in your system (such as the NVIDIA® graphics card, and the AJA Kona card), and how to connect your workstation to the peripherals you want to use it with (such as a pen tablet, graphics monitor, broadcast monitor, or VTR).

Preparing Your Media Storage

Before configuring storage to work with Autodesk Smoke, contact your storage vendor to make sure your storage fulfills the requirements for the frame format you will be working with.

Remember that, in order to ensure the best quality results, Autodesk Smoke does not apply compression to rendered intermediates. This means that the storage bandwidth requirements are higher than those for applications that use compressed media. Select the appropriate storage solution to achieve sustained real-time playback.

Consult the Autodesk Smoke for Mac OS X System Requirements Web page at www.autodesk.com/smoke-systemrequirements for guidelines about the throughput your storage should support for various frame formats.

Consult your vendor documentation for information on connecting the media storage disks to your Mac, and on using the Mac OS X Disk Utility to perform the RAID striping of your media storage device.

Recommended File System

For optimal performance, Autodesk recommends using the default *Mac OS Extended Journaled (HFS+)* file system, for your system drive and your media storage volume.

Use the Mac OS X Disk Utility to format your media storage volume to the recommended file system. Consult your Mac OS X documentation for information.

Updating Your Operating System

Consult the Autodesk Smoke for Mac OS X System Requirements Web page at www.autodesk.com/smoke-systemrequirements for information on the version of the Mac OS X operating system required for Autodesk Smoke.

To find out which version of Mac OS X your workstation is currently running, select About this Mac from the Apple menu. The version number appears below the *Mac OS X* heading.

If your workstation is not running the required version of Mac OS X, click Software Update to upgrade your operating system.

WARNING Do not update your operating system or hardware drivers to versions other than the ones recommended by Autodesk. Ignore any updates offered by the Apple Software Update utility, unless instructed otherwise by Autodesk.

Installing or Updating Hardware Drivers

Before installing Smoke, install or upgrade the drivers for your hardware devices.

Consult the Autodesk Smoke for Mac OS X System Requirements Web page at www.autodesk.com/smoke-systemrequirements for information on the supported driver versions.

You can update some of the drivers, such as the NVIDIA graphics card driver, through the Apple Software Update utility. To get drivers that are not installed by the Software Update utility (such as the AJA Kona video card driver, or the Wacom® pen tablet driver), refer to the Web site of your hardware device vendor.

WARNING Do not install any driver versions other than the ones recommended by Autodesk. Ignore any driver updates offered by the Apple Software Update utility, unless instructed otherwise by Autodesk.

Setting System Preferences

Open the System Preferences application, and set the following options as indicated in the table below.

WARNING These settings are mandatory and will prevent Smoke from working correctly if they are not set as documented.

NOTE These system preferences are set per Mac OS X user account. Make sure you apply them to all the Mac OS X user accounts you plan to use with Smoke.

System Preference	Option to Modify
Desktop & Screen Saver	In the Screen Saver tab, set <i>Start screen saver</i> to Never.
Energy Saver	<ul style="list-style-type: none">■ Set <i>Computer sleep</i> to never.■ Disable <i>Put the hard disk(s) to sleep when possible</i>.
Euphonix (if applicable)	Depending on current location of control surface Ethernet connection, Set <i>Network interface</i> to Ethernet Port 1 or Ethernet Port 2.
Keyboard	In the Keyboard tab, enable <i>Use F1, F2, etc. keys as standard function keys</i> .
Spotlight	In the Privacy tab, add the Smoke media storage volume to the list of locations Spotlight does not search.
Software Update	<p>In the Scheduled Check tab, disable <i>Check for updates</i>.</p> <hr/> <p>NOTE Before installing Mac OS X or QuickTime® updates, consult the Autodesk Smoke for Mac OS X System Requirements Web page at www.autodesk.com/smoke-systemrequirements, to see if these updates are compatible with the installed version of Smoke.</p> <hr/>
Sound	<p>In the Output tab, make sure the device selected for sound output is not the AJA card.</p> <p>Select, for example, <i>Internal Speakers</i>, or <i>Line Out</i>.</p> <hr/>

Configuring Your Network

Smoke for Mac OS X supports both static IP and DHCP network configurations.

If your Mac uses DHCP to obtain its hostname or IP address, make sure the hostname and IP address assigned to your computer do not change when the DHCP lease is renewed.

WARNING If the hostname or IP address of your Mac change while Smoke is running (for example, if your Mac switches from a wired network to a wireless connection), close Smoke and restart your computer, to avoid any issues with the application.

Configuring Mac OS X Keyboard Shortcuts

The Smoke application uses many keyboard shortcuts that are also used by Mac OS X.

As a general guideline, make sure your operating system does not use any single-key shortcuts (such as **F1**, **F2**, etc.) or shortcuts that include the **CTRL** and **OPTION** key modifiers, as these could overlap with Smoke hotkey combinations.

It is recommended to include the **COMMAND** key when defining OS-level shortcuts, as Smoke does not use this key.

Update your keyboard preferences as suggested below. These changes are optional but will minimize keyboard shortcut conflicts.

NOTE The keyboard preferences are set per Mac OS X user account. Make sure you apply them to all the Mac OS X user accounts you plan to use with Smoke.

To edit OS keyboard shortcuts:

- 1 Open the System Preferences application.
- 2 Click Keyboard.
- 3 In the Keyboard tab, enable *Use all F1, F2, etc. keys as standard function keys*.

NOTE This option is available only if you are using an Apple keyboard.

- 4 Click the Keyboard Shortcuts tab.




- 5 Select each section in the left panel, and then disable all its keyboard shortcuts, or change the shortcuts to include the **COMMAND** key.

Configuring Wacom Pen Buttons

To make sure the Wacom pen buttons work properly in Smoke, configure them as follows.

- 1 Open the System Preferences > Wacom Tablet panel.



- 2 If Grip Pen does not appear in the Tool section, touch the pen on the tablet.
- 3 Select the Pen tab.
- 4 Make sure the top pen button is assigned to the double-click function, and that the bottom pen button is assigned to the right-click function.

Installing and Licensing Smoke

3

Topics in this chapter:

- [About Trial License Installation](#) on page 9
- [About Installing Smoke with the Network License Server](#) on page 12
- [About Standalone License Installation](#) on page 20
- [Offline Registration and Activation](#) on page 24
- [Uninstalling Smoke](#) on page 25
- [Other Software](#) on page 26

About Trial License Installation

A trial license of Smoke lasts for 30-days. The “Days Remaining” in your trial appears in the Product License Activation window each time you start Smoke.


NOTE Do not use the Activate button from the Product License Activation window to activate a network license, which you receive for commercial and educational editions of Smoke. You must re-install Smoke to activate your network license. See [About Installing Smoke with the Network License Server](#) on page 12.

Installing the Trial Version Smoke

To install the trial version Smoke:

- 1 Locate the Smoke installer. Do one of the following:
 - If you are installing Smoke from a DVD, insert the DVD, and then double-click the DVD icon that appears on your desktop.

- If you are installing Smoke from a downloaded *.dmg* disk image file, double-click the file. The contents of the DVD or *.dmg* disk image are displayed.
- 2 Double-click *Install Smoke 2011 Extension 1*. The installer starts.
 - 3 Click Continue.
 - 4 In the Important Licensing Information window, be sure to read all of the information that appears in this window and then click Continue.




- 5 In the Product Information window, select “I want to try this product for 30 days”.




- 6 Depending on your OS configuration, the Select a Destination window may appear. Click “Install for all users of this computer”, and then click Continue.



- 7 In the Additional Content window, select Add Tutorial Content to install sample material that you can use to explore Smoke.



- 8 In the Media Storage window, click Select to define an internal or external storage volume for your media.



A file browser window opens.

- 9 Browse to the volume you want to use for media storage. The installer will automatically create a subfolder called *ManagedFolder7* under the folder you select, so that all Smoke media files are kept in one place.

WARNING Never use your Mac OS X system disk for media storage, as this may fill up the drive and impair system performance.

- 10 Type a name for your media storage folder in the Media Storage Name field. This name will also be used by Smoke to refer to your media storage folder.

NOTE This name can only contain non-accented latin letters and numbers. Do not use special characters.

- 11 Click Continue.
- 12 Click Install to begin the installation process.
Smoke is installed.
- 13 Start Smoke. In the Product License Activation window, click Try.

Converting from Trial to a Network License

When you purchase the commercial or educational edition of Smoke, you receive a network serial number and license.

You must re-install Smoke to install and configure the network license server. Do not click the Activate button to activate a commercial or educational edition of Smoke.

See [About Installing Smoke with the Network License Server](#) on page 12.

About Installing Smoke with the Network License Server

A network license is required for commercial and educational editions of Smoke.

NOTE If you have a trial version of Smoke installed, you must re-install Smoke to install and configure the license server. Do not use the Activate button from the Product License Activation window to activate a network license of Smoke.

With a network license, you must install a license server to manage the license.

- If you have only one Autodesk product running on a single workstation, the license server can be installed and set up for you automatically on the same workstation as Smoke. See [Installing Smoke with a Local Network License Server](#) on page 13.
- If you must manage multiple Autodesk licenses across your network, you must install and configure the license server on a dedicated workstation before you install Smoke. See [Network Licensing](#) on page 51.

Do not use the Activate button, unless you have a Student edition

If you have a Trial version of Smoke installed and you want to license it, do not use the Activate button in the Product License Activation window to activate your license. You must re-install Smoke. See [Installing Smoke with a Local Network License Server](#) on page 13.

Installing Smoke with a Local Network License Server

If you have a trial installed, you must reinstall Smoke to install and configure the license server.

Follow this procedure to install the license server on the same machine as Smoke.


NOTE If you have a version of Smoke older than Service Pack 4 installed on your workstation, you must uninstall it before you install, register, and activate Service Pack 4.

To install Smoke with a local network license server:

- 1 Locate your serial number. The serial number is located on the outside of the product packaging, or in the Autodesk® Upgrade and Licensing Information email.

NOTE If you have lost your serial number, contact the Autodesk Business Center (ABC) at 800-538-6401 for assistance.


- 2 Locate the Smoke installer. Do one of the following:
 - If you are installing Smoke from a DVD, insert the DVD, and then double-click the DVD icon that appears on your desktop.
 - If you are installing Smoke from a downloaded *.dmg* disk image file, double-click the file. The contents of the DVD or *.dmg* disk image are displayed.
- 3 Double-click *Install Smoke 2011 Extension 1*.
The installer starts.
- 4 Click Continue.
- 5 In the Important Licensing Information window, be sure to read all of the information that appears in this window and then click Continue.




6 Select “I have my product information” and enter your serial number.



7 In the License Type window, select Network License.



Network License Configuration window opens.



8 If you do not have your license file, you must register your product to receive your license file and continue the installation process.


Click the “Click here” link.

A browser window opens. You must create an Autodesk User ID, if you do not have one, and fill in all of the required information, including your serial number, Server host name and Server ID.

If you do not know the Server host name or Server ID of your machine:

- Look in the installer. This information appears in the Network License Configuration window if you have Use Local Machine selected.
- If you have advanced to another screen, you can get this information in the About This Mac window. See [Get Your License Server Hostname and Server ID Manually](#) on page 19.

NOTE Remove the colons “:” from the Mac address when you register your product on the Autodesk website.



You license appears in your browser window. Keep the window open while you continue the installation process. You can save this file anywhere on your machine with any name.

Continue with the installation.

9 In the Network License Configuration window, select the following:

- Single license server
- Use local machine



NOTE Make sure Use local machine is selected.


- 10 Copy and paste your license information into the License File window. Be sure not to overwrite any previous license entries.



- 11 Depending on your OS configuration, the Select a Destination window may appear. Click "Install for all users of this computer", and then click Continue.



- 12 In the Additional Content window, select Add Tutorial Content to install sample material that you can use to explore Smoke.



- 13 In the Media Storage window, click Select to define an internal or external storage volume for your media.



A file browser window opens.

- 14 Browse to the volume you want to use for media storage. The installer will automatically create a subfolder called *ManagedFolder7* under the folder you select, so that all Smoke media files are kept in one place.

WARNING Never use your Mac OS X system disk for media storage, as this may fill up the drive and impair system performance.

- 15 Type a name for your media storage folder in the Media Storage Name field. This name will also be used by Smoke to refer to your media storage folder.

NOTE This name can only contain non-accented latin letters and numbers. Do not use special characters.

- 16 Click Continue.
- 17 Click Install to begin the installation process.



Smoke is installed and ready to run.

If Smoke does not start, see [Troubleshooting License Errors](#) on page 40.


Get Your License Server Hostname and Server ID Manually

You must provide your license server hostname and server ID during the installation process.

In most cases, you will install the license server on the same machine as Smoke. You may consider installing the license server on another machine if you have multiple Autodesk products to manage.

To get your license server hostname and server ID:

- 1 Open About this Mac.



a. License Server Hostname b. License Server ID

- 2 Click More Info.
- 3 The Server hostname appears on the top left corner of the window and the Server ID is the Hardware MAC address.

NOTE Remove the colons ":" from the Mac address when you register your product on the Autodesk website.

About Standalone License Installation

A standalone license is only available for the student edition of Smoke. Student licenses do not require a license file or a license server.

When you register the student edition, you receive a serial number which is required during the installation and activation process. See Student License: Installing and Activating Smoke.

Installing and Activating the Student Edition of Smoke

- If you have a Trial installed, start Smoke, click Activate and follow the instructions on the website. You must have your serial number.
- If Smoke is not installed, use the following instructions.


NOTE If you have a version of Smoke older than Service Pack 4 installed on your workstation, you must uninstall it before you install, register, and activate Service Pack 4.

To install Smoke (student edition):


- 1 Locate your serial number. The serial number is located on the outside of the product packaging, or in the Autodesk® Upgrade and Licensing Information email.

NOTE If you have lost your serial number, contact the Autodesk Business Center (ABC) at 800-538-6401 for assistance.


- 2 Locate the Smoke installer. Do one of the following:
 - If you are installing Smoke from a DVD, insert the DVD, and then double-click the DVD icon that appears on your desktop.
 - If you are installing Smoke from a downloaded *.dmg* disk image file, double-click the file. The contents of the DVD or *.dmg* disk image are displayed.
- 3 Double-click *Install Smoke 2011 Extension 1*. The installer starts.
- 4 Click Continue.
- 5 In the Important Licensing Information window, be sure to read all of the information that appears in this window and then click Continue.



- 6 Select "I have my product information" and enter your serial number.




- 7 In the License Type window, select “Standalone license (Student Edition Only)”.




- 8 Depending on your OS configuration, the Select a Destination window may appear. Click “Install for all users of this computer”, and then click Continue.



- 9 Select Add Tutorial Content to install sample material that you can use to explore Smoke.



- 10 In the Media Storage window, click Select to define an internal or external storage volume for your media.



A file browser window opens.

- 11 Browse to the volume you want to use for media storage. The installer will automatically create a subfolder called *ManagedFolder7* under the folder you select, so that all Smoke media files are kept in one place.

WARNING Never use your Mac OS X system disk for media storage, as this may fill up the drive and impair system performance.

- 12 Type a name for your media storage folder in the Media Storage Name field. This name will also be used by Smoke to refer to your media storage folder.

NOTE This name can only contain non-accented latin letters and numbers. Do not use special characters.

- 13 Click Continue.
- 14 Click Install to begin the installation process.
Smoke is installed.
- 15 Start Smoke.
- 16 In the Product License Activation window, click Activate.
- 17 Enter your serial number and follow the steps to register and activate your product online. If you do not have an internet connection, see [Offline Registration and Activation](#) on page 24.

Offline Registration and Activation

If for some reason online registration and activation is not possible, you can still register and activate your product offline. Contact Autodesk by mail, fax, or phone. Your activation code is sent back to you by mail or fax.

E-mail Create an e-mail message with your registration information and send it to Autodesk.

Fax Enter your registration information, and fax the information to Autodesk.

Phone Provide your registration information to one of our representatives over the phone.

Use the numbers or e-mail address that correspond to your area:

Area	e-mail	Fax and Phone Numbers
United States, Canada Latin America	authcodes@autodesk.com	FAX: 800.225.6490 or 415.507.4937 Phone: 800.551.1490
Europe Middle East Africa	authcodes.neu@autodesk.com	Fax: +41 (32) 7239169
Asia Pacific	ap.register@autodesk.com	Fax: +65.6735.4857

Offline registration and activation is necessary under the following conditions:

- An online request has timed out
- A processing error occurred such as an invalid serial number


Uninstalling Smoke

Perform the following procedure to uninstall Autodesk Smoke from your Mac.

NOTE The License Server is not uninstalled when you uninstall Smoke. See Content reference to: Uninstall the Network License Manager.

To uninstall Smoke from your Mac:

- 1 If Smoke is running, exit it.
- 2 In Finder, go to the *Applications / Autodesk / Smoke 2011 Extension 1* folder.
- 3 Run the *Smoke 2011 Extension 1 Uninstaller* application, and follow the on-screen instructions to uninstall Smoke.
- 4 (Optional, for advanced users) Perform the following steps to completely remove all the files installed by Smoke on your system drive:
 - Open Finder, and click **COMMAND+SHIFT+G**.
 - In the dialog box that opens, enter */usr/discreet*.
The contents of the */usr/discreet* folder are displayed.



- Delete all the subfolders under the *discreet* folder, with the exception of the *clip*, *project* and *user* folders. These folders contain the data files of the projects and clips you created in Smoke, and might be useful next time you install Smoke.

Other Software

The following components are installed by default with Smoke:

- Autodesk Backburner Manager
- Autodesk Backburner Server
- Autodesk WiretapCentral
- Autodesk Wiretap Gateway
- Autodesk Backburner Media I / O Adapter
- License Server

Installing and Licensing Wiretap Gateway

Wiretap Gateway reads image media in a number of formats from any storage device, and streams it live as raw RGB to local or remote clients. When you import files using a Gateway Library from the Clip Library in Smoke, it is Wiretap Gateway that gives you access to those files.

By default, Wiretap Gateway is installed with Smoke and there is nothing more you have to do to make it work for your local installation of Smoke.

If you have a network license of Smoke, you can install up to two remote Wiretap Gateway servers to provide transcoding services to a number of other workstations throughout your network.

You must license remote Wiretap Gateway servers.

For instructions on installing and licensing Wiretap Gateway on remote workstations, see the *Autodesk Wiretap Central and Autodesk Wiretap Gateway Installation Guide*.

Installing and Licensing Autodesk Burn

Autodesk Burn is a Linux-based network processing solution. Burn allows you to render images in the background using low-cost systems and frees your workstation for more creative tasks.

Your distribution of Smoke comes with a distribution of Burn, which you can deploy on a Linux workstation on your network.

For information on installing and licensing Burn, see the *Autodesk Burn Installation and User Guide*.

Configuring Smoke

4

Topics in this chapter:

- [About Smoke Setup](#) on page 29
- [Configuring General Settings](#) on page 29
- [Defining the Video Preview Device](#) on page 31
- [Defining VTRs](#) on page 32
- [Configuring VTR Emulation](#) on page 32
- [Adding or Editing Media Storage Volumes](#) on page 33
- [Configuring Backburner Settings](#) on page 34
- [Configuring the License Server](#) on page 36
- [About Compatibility with Projects Created in Previous Versions of Smoke](#) on page 36
- [Upgrading Smoke Projects to the Current Version](#) on page 37
- [Transferring Clip Libraries from a Previous Project on a Remote Host to a 2011 Extension 1 Project](#) on page 38


About Smoke Setup

The Smoke Setup utility allows you to easily configure general Smoke settings, add or edit the media storage, configure background rendering, and configure licensing.

Run the Smoke Setup utility from the *Applications / Autodesk / Smoke 2011 Extension 1 / Utilities* folder.

Configuring General Settings

The General tab of the Smoke Setup utility enables you to configure the following application settings.



- **Video Device** Use this setting to specify the video output device to be used with Smoke. If your Mac is equipped with an AJA Kona 3 card, select KONA 3.
- **Audio Device** Use this setting to specify the audio output device to be used with Smoke. If your Mac is equipped with an AJA Kona 3 card, select AJA. Otherwise, select CoreAudio to use the default sound card of your workstation.

NOTE You can only use the AJA card as an audio device if you also set the AJA card as the video device. Similarly, you can only use CoreAudio if the AJA card is not set as the video device.

- **Reserved Application Memory** Use this field to specify the amount of memory allocated for Smoke frame buffers. In most cases, you should leave this setting to *Automatic*. The default configuration is sufficient for most projects, regardless of the different resolutions you may be working with.
- **Max Library Size** Use this setting to define the maximum size of any single clip library, in megabytes. The higher the value, the more memory the application uses. Using a larger value reduces memory fragmentation, which optimizes memory use.

NOTE To run Smoke, you must have at least 10 megabytes of free hard drive space in addition to the value set by this field.

- **Network Panel Display** Use this setting to filter the list of remote media storage volumes that are displayed in the Network panel. Select *ShowMounted* to see only media storage volumes that are mounted and available on the Wire network, or *ShowAll* to show all media storage volumes available on the network without checking whether they are mounted.

NOTE Using *ShowAll* slightly reduces the time needed for your application to start, as no checks are performed on remote media storage volumes.

- **Default Web Browser** Use this setting to specify the Web browser used by Smoke to browse the Help and view HTML tables of contents for archives. Set this option to *open* to use the default Web browser.

- **Cleaner Export Destination Path** If you are using Autodesk® Cleaner® XL digital video mastering and encoding software, use this field to define the default path on a Microsoft® Windows® workstation where clips are saved after encoding by Cleaner XL. The default path you enter appears in the Cleaner Destination Path field when you select *Cleaner* in the Format Box of the Image Export menu. You can edit the path there. If there is an ftp path in the output profile, the ftp path is used as an additional destination for encoded jobs. See your application help.
- **Archive Size** Use this field to define the maximum size for a file archive in MB. The default value is 1024MB.
- **Default Location** Use this field to define the default location for archives created in Smoke. The default location is */var/tmp/archive*.
- **Table of Contents Location** Use this field to define the location where online HTML and ASCII tables of contents are saved when archiving. The default location is */usr/discreet/archive*.

NOTE If you prefer to edit these parameters directly in the application configuration file, click Manual Edit. Be very careful when working with the configuration file. Incorrect settings may make your application unusable.


When you have finished configuring these settings, click Apply to save them. If you want to revert to the last saved configuration, click Reload. Note that this will undo unsaved changes in all the tabs of the Smoke Setup utility.

Defining the Video Preview Device

Use the Preview tab of the Smoke Setup utility to specify the device used for the graphics-to-video display.

Enable entries for the resolutions of the projects on which you will be working, as well as the resolutions supported by your hardware configuration.

If necessary, you can also add new entries, and duplicate or delete existing entries.




When you have finished configuring these settings, click Apply to save them. If you want to revert to the last saved configuration, click Reload. Note that this will undo unsaved changes in all the tabs of the Smoke Setup utility.

Defining VTRs

Use the Vtr tab of the Smoke Setup utility to specify the video tape recorders you want to use for clip I/O.

You can enable VTRs of different video formats. Any enabled VTR can be selected for a project, regardless of the project's video I/O timings.

If necessary, you can also add new entries, and duplicate or delete existing entries.




When you have finished configuring these settings, click Apply to save them. If you want to revert to the last saved configuration, click Reload. Note that this will undo unsaved changes in all the tabs of the Smoke Setup utility.

Configuring VTR Emulation

Use the Emulator tab of the Smoke Setup utility if you want to configure your workstation to emulate a Sony™ VTR.

You can specify more than one emulator. Any enabled emulator can be selected for a project, regardless of the project's video I/O timings.


If necessary, you can also add new entries, and duplicate or delete existing entries.



When you have finished configuring these settings, click Apply to save them. If you want to revert to the last saved configuration, click Reload. Note that this will undo unsaved changes in all the tabs of the Smoke Setup utility.

Adding or Editing Media Storage Volumes

Use the Media Storage tab of the Smoke Setup utility to define new media storage volumes for use with Smoke, or to edit the settings of existing media storage volumes.



To define a new media storage volume, click Add.

A new entry is created in the media storage list, and is populated with default values.

NOTE For safety reasons, the Name and Location fields are blank by default. You are required to fill in these fields before you can click Apply.

To edit the settings of a media storage folder:

- 1 Double-click the Name field and enter a meaningful label for the media storage. For example, *MyMedia*. This label identifies the media storage in Smoke.
- 2 Double-click the Location field, and browse to the directory that will contain the Smoke media files on your storage device. For example, */Volumes/G-SPEED/ManagedFolder7*.

WARNING Do not select the root of a drive as your media storage folder. Create a subfolder to hold all your media files in one place. We recommend that you name the subfolder *ManagedFolder<x>*, where *<x>* is the number that appears in the Id column in the Smoke Setup utility.

- 3 (Optional) Double-click the 8-bit Integer, 10-bit Integer, 12-bit Integer and 12-bit Packed Integer fields, and choose the file formats that Smoke will use when writing frames of those bit depths to the storage.
- 4 (Optional) If you plan to use the *JPG* file format, double-click the Jpeg Compression field, and set JPEG compression to a value between 0 (lowest compression, highest quality) and 100 (highest compression, lowest quality).
- 5 Click Apply to save your configuration.
If you want to revert to the last saved configuration, click Reload. Note that this will also undo any unsaved changes in the other tabs of the Smoke Setup application.


NOTE If you prefer to edit these parameters directly in the storage configuration file, click Manual Edit. Be very careful when working with the configuration file. Incorrect settings may make your application unusable.

Configuring Backburner Settings

If you want to use an Autodesk® Burn® background processing network, or to use your Mac as a background processing node, define Backburner settings in the Backburner tab of the Smoke Setup utility.

To configure background processing for Smoke, use the four fields in the Application Settings Section.

To use your Mac as a background processing node, define the hostname of the Backburner Manager that will distribute processing jobs to your Mac, in the Local Server Settings section.



To configure settings for jobs submitted by Smoke to a Backburner network:

- 1 In the Manager Hostname field of the Application Settings section, enter the hostname or IP address of the Backburner Manager system that will handle background jobs submitted by Smoke.
Setting the Manager Hostname enables the Background Wire[®] and Background Proxies buttons in the application; they are otherwise greyed out.
- 2 In the Job Priority field, enter the priority for jobs sent by Smoke to the Backburner Manager on your rendering network. Job priority can range from 0 to 100, where 0 is the highest priority and 100 is the lowest. The default is 50.
- 3 In the Server Group field, enter the name of the group of render nodes to which jobs created in Smoke will be submitted. Refer to the latest *Autodesk Backburner User Guide* for information on creating groups in Backburner Monitor.
- 4 From the Group Capability drop-down list, select whether the nodes in your group are equipped with GPU-accelerated graphics cards or not.

Set this value as follows:

- If none of the nodes in your rendering network are equipped with GPUs, select *software*. Smoke will not send jobs that require a GPU to the rendering network, but only jobs that can be rendered in software mode by the render nodes.
- If **ALL** the nodes in your rendering network are equipped with GPUs, select *gpu*. Smoke will send all jobs to the GPU-equipped nodes, even if some jobs do not specifically require a GPU render node.

NOTE If your rendering network also contains render nodes without a GPU, but this value is incorrectly set to *gpu*, all jobs are sent only to GPU-equipped render nodes, and the nodes without a GPU are never used.


- If your rendering network contains a mix of nodes with GPUs and without GPUs, select *hybrid*. The application sends all jobs to the rendering network, and Backburner Manager distributes each job to the appropriate type of render node.

NOTE Select *gpu* or *hybrid* only if you are sure that at least one node in your rendering network is equipped with a GPU. Attempting to submit a job that requires a GPU to a rendering network with no GPU-equipped render node results in the job being stuck in the rendering queue indefinitely.

Configuring the License Server

You can use the Licensing tab to configure the location of your license server.

- To set the current workstation as your license server, click Add Localhost and click Apply. The license server must be installed on the local workstation. See [Installing Smoke with a Local Network License Server](#) on page 13.
- To identify another workstation as the license server, click +, enter the name in the hostname field, and then click Apply. The license server must be installed on the remote workstation. See [Network License Manager](#) on page 60.



About Compatibility with Projects Created in Previous Versions of Smoke

Projects and clip libraries created in previous versions of Smoke are read-only.

- If the original project is on the same system, create a project in 2011 Extension 1 and then copy the clip libraries from the old project to the new project. If you have many projects to upgrade, use the project upgrade script to create the 2011 Extension 1 projects for you. See [Upgrading Smoke Projects to the Current Version](#) on page 37.

- If the original project is on another system that has a previous version installed, transfer (push) the clip libraries to a project on the 2011 Extension 1 system. See [Transferring Clip Libraries from a Previous Project on a Remote Host to a 2011 Extension 1 Project](#) on page 38
- Alternatively, you can archive the project from an older version and restore the archive in the latest version. See the application help for instructions on creating and restoring archives.

NOTE Projects and clip libraries of a service pack for the same version are compatible.

Upgrading Smoke Projects to the Current Version

NOTE You do not need to perform this task if you are upgrading to a service pack of the same version.

Use the *copyProjects* command-line tool to recreate Smoke projects from previous versions in the latest version.

Using this tool instead of manually re-creating your projects is the recommended approach, as it reduces the time needed to migrate multiple projects, and prevents human error.

NOTE The *copyProjects* tool does not copy any media. It only re-creates projects and copies their settings and setups to the current version. You still have to transfer your media using the network library.

To copy projects using the *copyProjects* tool:

1 Open a the Terminal (*/Applications/Utilities*) and log in as root.

2 Go to the location of the *copyProjects* script. Type:
cd /usr/discreet/<smoke_version>/bin

3 Launch the script. Type:
./copyProjects

The tool detects all projects from previous versions, and returns the following message:

```
Projects will be copied to version 2011 Extension 1
Do you wish to continue?
```

NOTE You can also run the *copyProjects* command with the *-s* parameter to change the suffix that the script adds to the new copies of projects. For example: `/usr/discreet/<product_home>/bin/copyProjects -s _2011ext1`

4 If the version returned by the script is the newly installed version, answer Yes and continue this procedure. Otherwise, perform the steps in the following procedure to change the application version to which projects are copied.

5 Confirm each project you want to copy to the new version, or type “a” to copy all projects.
If you don't use the *-s* parameter, the default suffix *_copy* is appended to the names of the copied projects (e.g. *myProject* will be copied as *myProject_copy*)

6 Use the network library to transfer media into the copied projects.

To change the application version projects are copied to:

1 Open a terminal and log in as root.

2 Stop Stone and Wire by typing:
`/usr/discreet/sw/sw_stop all`

3 Unlink the Wiretap startup script by typing:

```
unlink /usr/discreet/sw/sw_depend/ifffsWiretapServer.sw_depend
```

- 4 Link the Wiretap startup script to the latest version by typing:

```
ln -s /usr/discreet/wiretap/<version>/ifffsWiretapServer.sw_depend  
/usr/discreet/sw/sw_depend/ifffsWiretapServer.sw_depend
```

- 5 Start Stone and Wire by typing:

```
/usr/discreet/sw/sw_start all
```

- 6 Run the copyProjects script again.

Transferring Clip Libraries from a Previous Project on a Remote Host to a 2011 Extension 1 Project

To access clip libraries from projects created with Smoke versions 2010 or 2011 on a remote host with 2011 Extension 1, you must transfer the clip libraries to a project created in version 2011 Extension 1.

You can install version 2011 Extension 1 on the remote system and use Wire to transfer the clip libraries to a version 2011 Extension 1 project. See your application help.

If you do not want to or cannot install Smoke 2011 Extension 1 on the remote system, use the following procedure to transfer clip libraries between two versions.

To transfer clip libraries to a 2011 Extension 1 project:

- 1 Use Smoke 2010 or 2011 to create a project and a clip library on the 2011 Extension 1 system. See your application help. The project and library is formatted for the software version it was created with.
- 2 Use the 2010 or 2011 application to move clips over the network into the previously created project on the 2011 Extension 1 system. You can use Background Wire to help free up the resources of the workstation running the older version of the application. See your application help.
- 3 Create a new project on the version 2011 Extension 1 system. If you have many projects, use the *copyProjects* script.
- 4 Use the 2011 Extension 1 application to open the library created in step 1 (the library is read-only).
- 5 Use Dual View to drag the clips into the 2011 Extension 1 project and library.
- 6 Use the older application version to remove the project created in step 1. 2011 Extension 1 applications cannot remove projects created with previous versions because they are read-only.

TIP If you have 2010 or 2011 installed on your 2011 Extension 1 system, you can access the 2010 or 2011 system remotely to transfer the media using Wire without interrupting a session on that station. See your application help.

Troubleshooting Smoke Installation, Licensing and Configuration

5

Topics in this chapter:

- [Invalid Serial Number Error](#) on page 39
- [Troubleshooting License Errors](#) on page 40
- [Enabling Remote Login](#) on page 43
- [Viewing Application Error Messages](#) on page 44
- [Checking that Background Services are Running](#) on page 44
- [Forcing Smoke to Exit](#) on page 45
- [Handling System Freezes](#) on page 46
- [Repairing Media Storage Mount Points](#) on page 46
- [Fixing VOLUMEMGT and No Volume Errors](#) on page 47
- [Rebooting after an IP Address or Host Name Change](#) on page 47
- [Sending Application Logs to Autodesk Customer Support](#) on page 47
- [Switching Your Mac OS X Kernel between 32-bit Mode and 64-bit Mode](#) on page 48

Invalid Serial Number Error

If you click the Activate button and enter a network license serial number, you will get an “Invalid serial number” error.

To go from a trial to commercial or educational license of Smoke, you must re-install Smoke to install and configure the network license server.

See [About Installing Smoke with the Network License Server](#) on page 12.

Troubleshooting License Errors

Follow these procedures if you are unable to start Smoke due to license errors.

To troubleshoot license errors:

- 1 Check that Smoke is using the right license server. See [Verifying the License Server](#) on page 40.
- 2 If you are using DHCP (Dynamic Hostname Configuration Protocol), the name of the license server might change and cause license errors. See [Troubleshooting Hostname Changes](#).
- 3 If Smoke does not start and you are still getting license errors, restart the license server using the License Server Configurator. See [Restarting the License Server](#) on page 41.
- 4 If Smoke does not start and you are still getting license errors, check the license and then restart the license server. See [Verifying the License File](#) on page 42.


Verifying the License Server

If you are getting license errors when starting Smoke, you should first check that Smoke is pointing to the right license server.

In most cases, the license server is installed on the same workstation as Smoke.

To verify the license server:

- 1 Start Smoke Setup. Smoke Setup can be found in the *Applications/Smoke 2011/Utilities* folder.
- 2 Open the Licensing tab.



- 3 Click the - button to remove a license server from the list.
- 4 Do one of the following:
 - Click Add localhost to use the current workstation as the license server.

- Click + and then type the hostname of the license server in the Hostname field.
- 5 Click Apply to confirm any changes.
You must restart Smoke to confirm if it starts with the new license server.
If Smoke does not start, try re-starting the license server. See [Restarting the License Server](#) on page 41.

Licensing Errors Caused by DHCP Problems

Smoke does not start if the machine cannot resolve its own hostname. This can be caused by DHCP hostname change, a missing DNS suffix, or a missing .local hostname suffix in the license file.

To fix licensing errors caused by DHCP problems:


- 1 Open the License Server Selector from *Applications/Autodesk/Smoke Common Utilities*.
- 2 Select the License Server currently in the list, and then click the "-" (minus) button to remove it.
- 3 Click Add Localhost. The License server hostname should be "127.0.0.1". Click Ok.
- 4 Open the License Server Configurator from *Applications/Autodesk/Smoke Common Utilities*.
- 5 Click the Licensing tab. Change the server name in the license for "localhost" (i.e: SERVER server_name 002500ef9055 to SERVER localhost 002500ef9055).
- 6 Click Apply.
- 7 Click the Server Status tab, and click Restart to restart the server. Re-start Smoke.

Restarting the License Server

The License Server can be installed on the same workstation as Smoke. Or, it may be installed on another workstation to manage multiple Autodesk licenses across a facility.

To restart the license server:

- 1 Open the Service Monitor. You can find the Service Monitor in this location: */Applications/Autodesk/Smoke Common Utilities/Service Monitor/*



2 Do one of the following:

- If the server is not running, click Start.
- If the server is running, click Stop and then Start or just Restart.


If you get error messages when you start Smoke after restarting the license server, validate the license file and restart the license server again. See [Verifying the License File](#) on page 42.

Verifying the License File

If you are having problems with the license server, verify that the license server is using the Smoke license.

To verify the license file:

- 1 Open the License Server Configurator. You can find the License Server Configurator in one of the following places:
 - If Smoke is installed on the same workstation: *Applications/Smoke 2011/Utilities*
 - If Smoke is not installed on the workstation: */Applications/Autodesk/Adlm*



- 2 Click the Licenses tab.



- 3 Cut and paste the license into the Licenses window or open the license file that you saved locally.
- 4 Click Apply and then restart the license server.

Enabling Remote Login

To ensure you will be able to reboot your workstation if it freezes, it is recommended that you enable remote login on your Mac.

To enable remote login:

- 1 Open System Preferences, and click Sharing.
- 2 Enable Remote Login. Allow access to all users by selecting "All users".
- 3 Close System Preferences.

Viewing Application Error Messages

If you experience problems with Smoke or any of its related components, checking the error messages in the Mac OS X system console might help you to identify the issue.

To view Smoke error messages:


- 1 Open the Console application from the *Applications / Utilities* folder.
- 2 From the File menu, click New Database Search.



- 3 Give your search a meaningful name. You will be able to reuse it later.
- 4 Define the search criteria as illustrated in the previous screenshot, and click OK.
A new Console window opens and displays all messages sent by Autodesk applications or services, and containing the words “error”, “failed” or “failure”. The search settings are saved in the left panel of the Console window, under Database Searches.
- 5 Look through the error messages to find any information that might help you identify the problem. If you encounter error messages about Backburner or Stone and Wire, refer to the following section for information on restarting these services.

Checking that Background Services are Running

To check that all necessary background services are running, open the Service Monitor application from the *Applications / Autodesk / Smoke Common Utilities* folder.




A green status light means that a service is running. A red light means that the service is not running. Click Restart to activate it.

WARNING Before stopping or restarting a background service, make sure Smoke is not running, and that there are no network connections to your media storage.

Forcing Smoke to Exit

If Smoke crashes but does not close, use the following procedures to force it to quit.

- 1 Run the Service Monitor application from the *Applications / Autodesk / Smoke Common Utilities* folder.
- 2 Click the Troubleshooting tab.



- 3 Click NOW! to force Smoke to quit.
- 4 If Smoke still does not quit, use the following procedure to exit Smoke from the Terminal.

To exit Smoke from the Terminal:

- 1 Open the Terminal from the *Applications / Utilities* folder.
- 2 Type: `sudo killall -9 smoke`

- 3 Press **Enter**.
- 4 Enter your password and press **Enter**.

Handling System Freezes

If your workstation “freezes” for any reason, **DO NOT** force it to power off using the Power button, as this may cause problems with your media storage.

To avoid any problems, always use the following procedure to safely restart your workstation when it freezes.

To reboot your Mac OS X workstation:

- 1 On a Linux® system or another Mac on your network, open a terminal and type the following command to connect remotely to the Smoke Mac OS X workstation:

```
ssh <user_name>@<Mac_IP_Address>
```

Where <user_name> is a user that exists on the Smoke Mac OS X workstation, or a NIS (network) user, and <Mac_IP_Address> is the IP address of the Smoke Mac OS X workstation. You can also use the workstation hostname instead of the IP address.

NOTE You can also connect from a Windows® system, by installing a SSH client such as *OpenSSH*.

- 2 Enter your password when prompted.
- 3 When you are logged into the Mac OS X workstation, type the following command to reboot it:
sudo reboot
- 4 Enter your password when prompted.
The workstation reboots.

Repairing Media Storage Mount Points

If you force your workstation to power off, the operating system may mount the storage on an incorrect mount point folder when it restarts (for example, */Volumes/Storage1* instead of */Volumes/Storage*). This issue prevents Smoke from being able to access the media storage.

To avoid this problem, **NEVER** use the Power button to force a shutdown if your workstation freezes. Use the procedure described in the previous section to safely reboot your workstation.

If you did force the workstation to power off, and are now experiencing storage issues, perform the following procedure to delete the incorrect mount point, and to mount your storage to the proper mount point.

To delete an incorrect mount point:

- 1 Log into your workstation as a user with administrative privileges.
- 2 Open System Preferences, click Sharing, and disable all the file services.
- 3 Open Finder.
- 4 Press **COMMAND+Shift+G**, and type */Volumes* in the text field.
- 5 In the */Volumes* folder, locate the incorrect mount point folder. It should have the name of the original mount point (for example, *Storage*), but its icon depicts a folder instead of a disk drive.
- 6 Right-click the incorrect mount point folder, and select “Move to Trash” from the context menu. Enter your password if prompted.

The folder is deleted.

7 Restart your workstation.

The media storage should mount to the proper location (for example, */Volumes/Storage*) after the reboot.

NOTE If the media storage is still not available after restart, open Disk Utility from the *Applications / Utilities* folder, select your media storage disk, and click Repair Disk in the First Aid tab. See the Mac OS X documentation for details.

Fixing VOLUMEMGT and No Volume Errors

Follow the steps below if you ever start Smoke and cannot select your framestore volume, or if you get the following error:

Error: VOLUMEMGT : Failed to initialize Stone+Wire connection.

To solve the errors listed above:

- 1 Exit Smoke.
- 2 Open the Service Monitor application from the *Applications / Autodesk / Smoke Common Utilities* folder.
- 3 Restart the *Stone+Wire* service.
- 4 Start Smoke.

Rebooting after an IP Address or Host Name Change

If your workstation uses DHCP to obtain its network configuration, it is advisable to restart it after a change of IP address, for instance, when switching from a wired to a wireless connection.


Furthermore, ensure that your workstation's hostname remains constant and is resolvable at all times in the DHCP environment, as the media storage and networking components of Smoke (known as "Stone and Wire") do not support dynamic hostname changes.

Sending Application Logs to Autodesk Customer Support

If you have contacted Autodesk Customer Support to troubleshoot an issue with your application, you may be asked to submit the application log files.

To submit Smoke log files to Autodesk:

- 1 Make sure your Mac is connected to the Internet.
- 2 Run the Service Monitor application from the *Applications / Autodesk / Smoke Common Utilities* folder.
- 3 Click the Troubleshooting tab.



- 4 Click Send.

Smoke and system log files are automatically sent to Autodesk.

Switching Your Mac OS X Kernel between 32-bit Mode and 64-bit Mode


Smoke 2011 Extension 1 for Mac OS X is a 64-bit application that can run on either the 32-bit Mac OS X kernel or the 64-bit kernel, while Smoke 2010 for Mac OS X specifically required the 64-bit kernel.

If you are running Smoke 2011 Extension 1 for Mac OS X on a workstation where Smoke 2010 for Mac OS X was previously installed, you may need to switch the Mac OS X kernel into 32-bit mode for certain third-party drivers and software to work properly.

Skip this section if you are running Smoke 2011 Extension 1 for Mac OS X on a workstation where Smoke 2010 for Mac OS X was never installed. By default, Mac OS X comes with the 32-bit kernel activated, which can run most 64-bit applications, including Smoke 2011 Extension 1.

To switch the kernel between 32-bit mode and 64-bit mode:

- 1 Run the Service Monitor application from the *Applications / Autodesk / Smoke Common Utilities* folder.
- 2 Click the Troubleshooting tab.



- 3 Click the 32 bit or 64-bit button.
- 4 Reboot your Mac for the change to take effect.

Appendix: Autodesk Licensing

Includes these chapters:

- [Network Licensing](#) on page 51
- [Stand-Alone Licensing](#) on page 69
- [Licensing Glossary](#) on page 75

Network Licensing

A

Topics in this chapter:

- [Introduction](#) on page 51
- [Plan Your Network Licensing](#) on page 51
- [Network License Manager](#) on page 60
- [Network Licensing Tools](#) on page 63
- [License Borrowing](#) on page 64

Introduction

A network license allows you to run an Autodesk product on a network. Network licenses can be purchased through your Authorized Autodesk Reseller.

Setting up network licenses for an Autodesk product requires careful planning and execution. This section gives you instructions about how to set up a network licensed environment, and assumes that you are familiar with the terminology and processes required to set up an Autodesk product to run on a network.

Plan Your Network Licensing

This section contains information that you need to know before you set up a network license server. The section includes information about supported license server models, license operation and availability, network license file definitions and parameters, license file examples, license types and behaviors, and the license server heartbeat signal.

System Requirements for the Network License Manager (Windows)

Make sure that your network license server meets the minimum recommended requirements. See the following tables for hardware and software requirements.

NOTE The Network License Manager supports Ethernet network configurations only.

Hardware and software requirements for the network license server (Windows)

Hardware/Software	Requirement
Operating System	Windows® 7® 32-bit
	Windows 7 64-bit
	■ Windows 7 Starter (32-bit)
	■ Windows 7 Home Basic (32-bit)
	■ Windows 7 Home Premium
	■ Windows 7 Professional
	■ Windows 7 Ultimate
	■ Windows 7 Enterprise
	Windows Vista 32-bit SP2 or later
	Windows Vista 64-bit SP2 or later
	■ Windows Vista Enterprise
	■ Windows Vista Business
	■ Windows Vista Ultimate
	■ Windows Vista Home Premium and Basic (32-bit)
	■ Windows Vista Home Premium (64-bit)
	Windows XP 32-bit SP2 or later
	Windows XP 64-bit SP2 or later
	■ Windows XP Home
	■ Windows XP Professional
	Windows Server 32-bit SP1 or later
	Windows Server 64-bit SP1 or later
	■ Windows 2008 Server R2
	■ Windows 2008 Server
	■ Windows 2003 Server R2
	■ Windows 2003 Server
Computer/processor	Intel® Pentium® III or higher 450 Mhz (minimum)
Network interface card	Compatible with existing Ethernet network infrastructure NOTE The Network License Manager supports multiple network interface cards, but at least one must be an Ethernet card.
Communication protocol	TCP/IP NOTE The Network License Manager uses TCP packet types.
Browsers	Internet Explorer® 6 Internet Explorer 7 Internet Explorer 8

Hardware and software requirements for the network license server (Windows)

Hardware/Software	Requirement
FLEXnet	11.7.0.0

Virtual Machine Support (Windows)

Hardware	Virtualizer	Virtual OS
Intel PC 64	Windows 2008 or Windows 2003R2 servers running on VMware® ESX3.5 Update 3 (License Manager Only)	Vista 64-bit, Vista 32-bit, Windows XP 32-bit, Windows 7 32-bit (Home Premium, Professional, Ultimate, and Enterprise), Windows 7 64-bit, Windows Server 32-bit, Windows Server 64-bit

System Requirements for the Network License Manager (Mac OS X)

Make sure that your network license server meets the minimum recommended requirements. See the following tables for hardware and software requirements.

NOTE The Network License Manager supports Ethernet network configurations only.

Hardware and software requirements for the network license server (Mac OS X)

Hardware/Software	Requirement
Operating system	Mac OS® X version 10.6 and later
Computer/processor	Intel Mac
Network interface card	Compatible with existing Ethernet network infrastructure NOTE The Network License Manager supports multiple network interface cards, but at least one must be an Ethernet card.
Communication protocol	TCP/IP NOTE The Network License Manager uses TCP packet types
Browsers	Safari 4.0
FLEXnet	11.7.0.0

System Requirements for the Network License Manager (Linux)

Make sure that your network license server meets the minimum recommended requirements. See the following tables for hardware and software requirements.

NOTE The Network License Manager supports Ethernet network configurations only.

Hardware and software requirements for the network license server (Linux)

Hardware/Software	Requirement
Operating system	Linux® 64-bit Red Hat® Enterprise Linux 5.0 WS (U4)

Hardware and software requirements for the network license server (Linux)

Hardware/Software	Requirement
Computer/processor	Intel Pentium 3 or higher 450 Mhz (minimum)
Network interface card	Compatible with existing Ethernet network infrastructure NOTE The Network License Manager supports multiple network interface cards, but at least one must be an Ethernet card.
Communication protocol	TCP/IP NOTE The Network License Manager uses TCP packet types
FLEXnet	11.7.0.0

Plan Your License Server Configuration

You must decide which license server model to use for managing your Autodesk product licenses on a server. Autodesk supports the following network license server models:

- Single license server model
- Distributed license server model
- Redundant license server model

Single License Server Model

In the single license server model, the Network License Manager is installed on a single server, so license management and activity is restricted to this server. A single license file represents the total number of licenses available on the server.

Advantages of the Single License Server Model

- Because all license management takes place on a single server, you have just one point of administration and one point of failure.
- Of the three license server models, this configuration requires the least amount of maintenance.

Disadvantage of the Single License Server Model

- If the single license server fails, the Autodesk product cannot run until the server is back online.

Distributed License Server Model

In the distributed license server model, licenses are distributed across more than one server. A unique license file is required for each server. To create a distributed license server, you must run the Network License Manager on each server that is part of the distributed server pool.

Advantages of the Distributed License Server Model

- Servers can be distributed across a wide area network (WAN); they do not need to exist on the same subnet.

- If one server in the distributed server pool fails, the licenses on the remaining servers are still available.
- If you need to replace a server in the distributed server pool, you do not need to rebuild the entire pool.
- Server replacement is easier than in a redundant server pool, where you must reactivate the entire pool.

Disadvantage of the Distributed License Server Model

- If a server in the distributed server pool fails, the licenses on that server are unavailable.

Redundant License Server Model

In the redundant license server model, you use three servers to authenticate a single license file. One server acts as the master, while the other two provide backup if the master server fails. With this configuration, licenses continue to be monitored and issued as long as at least two servers are still functional. The license file on all three servers is the same. You must install the Network License Manager on each server.

In the redundant license server model, all servers must reside on the same subnet and have consistent network communications. (Slow, erratic, or dial-up connections are not supported.)

Advantage of the Redundant License Server Model

- If one of the three servers fails, all licenses that are managed in the server pool are still available.

Disadvantages of the Redundant License Server Model

- If more than one server fails, no licenses are available.
- All three servers must reside on the same subnet and have reliable network communications. The redundant server pool does not provide network fault tolerance.
- If one of the three servers is replaced, the complete redundant server pool must be rebuilt.
- If your Autodesk product supports license borrowing and licenses are borrowed from a redundant license server pool, you must restart the license server after you stop the Network License Manager.

Learn About Your License

In this section, you learn about license operation and availability, the license file, license types and behaviors, and the heartbeat signal.

License Operation and Availability

When you start an Autodesk product, the product determines the server from which it should try to obtain a license. The product then requests a license through the TCP/IP network protocol to the license server.

If the number of available licenses has not been exceeded on the license server, the Network License Manager assigns a license to the workstation. A product session then starts on the workstation, and the number of available licenses on the license server is reduced by one.

Likewise, when you exit a product, the Network License Manager frees a license for another user. If you run multiple sessions of an Autodesk product on an individual workstation, only one license is used. When the last session is closed, the license is freed.

The following three processes manage the distribution and availability of licenses:

- **License manager daemon** (*lmgrd.exe*). Handles the original contact with the application, and then passes the connection to the vendor daemon. The *lmgrd.exe* daemon is used to communicate with the vendor daemon only; *lmgrd.exe* does not authenticate or dispense licenses, but rather passes user requests to the vendor daemon. By using this approach, a single *lmgrd.exe* daemon can be used by multiple software vendors to provide license authentication. The *lmgrd.exe* daemon starts and restarts the vendor daemons as needed.
- **Autodesk vendor daemon** (*adskflex.exe*). Tracks the licenses that are checked out and the workstations that are using them. Each software vendor has a unique vendor daemon to manage vendor-specific licensing. As its name implies, the *adskflex.exe* vendor daemon is specific to Autodesk products.

NOTE If the *adskflex.exe* vendor daemon terminates for any reason, all users lose their licenses until *lmgrd.exe* restarts the vendor daemon or the problem causing the termination is resolved.

- **License file.** A text file that has vendor-specific license information.

License Files

The network license file you receive from Autodesk contains licensing information required for a network installation. You obtain license file data when you register your Autodesk product.

The license file contains information about network server nodes and vendor daemons. It also contains an encrypted digital signature that is created when Autodesk generates the file.

The license file is located in a network location that you specify in the Deployment wizard. That network location must be accessible to every user who runs the product from a network installation.

The following table defines each license file parameter.

Definitions of license file parameters			
Line	Parameter	Definition	Example
SERVER	Host Name	Host name of the server where the Network License Manager resides	LABSERVER
	Host ID	Ethernet address of the server where the Network License Manager resides	03D054C0149B
USE_SERVER	[None]		
VENDOR	Vendor Daemon	Name of the server-side Autodesk vendor daemon	<i>adskflex.exe</i>
	Port Number	Network port number reserved and assigned for use only by Autodesk products running the Autodesk vendor daemon	port=2080
PACKAGE	Name	Name of feature code group	<i>SERIES_1</i>
	Version	Internal version number reference	1.000
	COMPONENTS	List of feature codes supported in the package	COMPONENTS= "526000REVIT_9_OF\ 51200ACD_2007_OF\ 513001INVBUN_11_OF"

Definitions of license file parameters

Line	Parameter	Definition	Example
	OPTIONS		OPTIONS=SUIE
	SUPERSEDE	Replacement for any existing Increment line of the same feature code from any license files on the same license server that have a date earlier than the defined Issue Date	SUPERSEDE
	SIGN	Encrypted signature used to authenticate the attributes of the license file	SIGN=0 SIGN2=0
INCREMENT	Feature Code	Product supported by the license file	51200ACD_2007_OF
	Expiration Date	Amount of time the licenses are available	permanent
	Number of Licenses	Number of licenses supported by the license file	25
	VENDOR_STRING	License usage type and license behavior of the product that is supported by the license file	COMMERCIAL
	BORROW	Definition of the license borrowing period for the licenses defined under the same increment line. In this example, the maximum period that licenses can be borrowed is 4320 hours (180 days), unless otherwise noted (for example, BORROW=2880 means that licenses can be borrowed for a maximum of 2880 hours, or 120 days). License borrowing is disabled when this parameter is absent in the license file.	BORROW=4320
	DUP_GROUP	Definition of multiple license requests when the same user and same host share the same license	DUP_GROUP=UH
	ISSUED	Date that the license file was generated by Autodesk	15-jul-2006
	Serial Number	Serial number of the Autodesk product	123-12345678
	SIGN	Encrypted signature used to authenticate the attributes of the license file	SIGN=6E88EFA8D44C

License File Examples

License file examples are provided in this document to help you understand how the license files work for your particular network setup. Autodesk provides a standard license file for individual products and a license file with additional parameters for products that are sold both individually and as part of a product set.

- **Standard License File.** If you purchase one or more individual products that are not offered as part of a suite of products, you receive a standard license file.

- **Standard License File with Additional Parameters.** If you purchase Autodesk products that are included in a product set and are also sold as an individual product, you receive a standard license file with additional parameters included in the license file. The additional parameters define the sequence for license usage so that the individual product license is used before the license for the product set.

Autodesk license file examples include a license file not specific to a product, completed license files for single, distributed, and redundant server models, a combined product version license file, and an example of additional parameters added to a standard license file.

Example of a License File Not Specific to a Product

Here is an example of the contents of a license file and the parameters associated with each line:

```
SERVER ServerName HostID
USE_SERVER
VENDOR adskflex port=portnumber
INCREMENT feature_code Adskflex Version ExpDate NumberofLicenses \
  VENDOR_STRING=UsageType:Behavior BORROW=4320 SUPERSEDE \ DUP_GROUP=DupGrp ISSUED=IssueDate
  SN=SerialNumber SIGN= \
```

Example of a License File for a Single or Distributed Server

Here is an example of a completed license file for a single or distributed license server model:

```
SERVER XXHP0528 0019bbd68993
USE_SERVER
VENDOR adskflex port=2080
INCREMENT 57600ACD_2009_0F adskflex 1.000 permanent 5 \
  VENDOR_STRING=commercial:permanent BORROW=4320 SUPERSEDE \
  DUP_GROUP=UH ISSUED=09-Jan-2008 SN=123-12345678 SIGN="1393 \
  E368 816E D417 C1CD 7DBD 7B90 1354 D6F0 48FE EBB8 9C84 C3AF \
  7D79 BEE1 0181 0655 76FF 996C B707 14B5 D4DE A3FE 0B2D 2D36 \
  057C A579 7866 26BF 44E2" SIGN2="1280 943B 53A7 9B93 E00B D967 \
  D821 BD37 BE6D B78A F074 B223 88AA 242C DD0A 1292 D56F 4108 \
  62CD FA35 E365 0736 A011 7833 8B35 7BFF DAD8 34A8 452F 2EB4"
```

Example of a License File for a Redundant Server

Here is an example of a completed license file for a redundant license server model:

```
SERVER CCN12378042 001cc4874b03 27005
SERVER XXHP0528 0019bbd68993 27005
SERVER CCN12378043 001cc4874b10 27005
USE_SERVER
VENDOR adskflex port=2080
INCREMENT 57600ACD_2009_0F adskflex 1.000 permanent 5 \
  VENDOR_STRING=commercial:permanent BORROW=4320 SUPERSEDE \
  DUP_GROUP=UH ISSUED=10-Jan-2008 SN=123-12345678 SIGN="11C4 \
  CA79 07FC 7AD0 409A 6E04 6E98 D76C 197C 0416 076C B211 1CDD \
  D0AB 698B 16BF 7A0E D4F8 1CFE 2985 644F 64CD CECE 0DDB 5951 \
  3262 7C31 13A8 F08F 55B2" SIGN2="19A6 FDA3 2ED5 5301 8675 7B81 \
  1B0E 451B 19F1 1A99 C8E9 CBA6 8CB3 6AC3 8B38 1519 13F2 2373 \
  82AE 55E5 1A25 4952 4458 F3A2 6F28 D25D 1DC0 E066 209B 0953"
```

NOTE The redundant server model requires the addition of a port number (the default is 27005) for each server.

Example of a License File for Combined Autodesk Product Versions

You can combine a license file for different releases of the same Autodesk product or for different Autodesk products, and run all products from one license server. For example, you can combine a license file for AutoCAD 2009 with license files for Autodesk Maya® 2009 and AutoCAD Map.

Here is an example of the contents of a combined license file for AutoCAD 2008 and AutoCAD 2009:

```
SERVER XXHP0528 0019bbd68993
USE_SERVER
VENDOR adskflex port=2080
INCREMENT 57600ACD_2009_0F adskflex 1.000 permanent 5 \
  VENDOR_STRING=commercial:permanent BORROW=4320 SUPERSEDE \
  DUP_GROUP=UH ISSUED=09-Jan-2008 SN=123-12345678 SIGN="1393 \
  E368 816E D417 C1CD 7DBD 7B90 1354 D6F0 48FE EBB8 9C84 C3AF \
  7D79 BEE1 0181 0655 76FF 996C B707 14B5 D4DE A3FE 0B2D 2D36 \
  057C A579 7866 26BF 44E2" SIGN2="1280 943B 53A7 9B93 E00B D967 \
  D821 BD37 BE6D B78A F074 B223 88AA 242C DD0A 1292 D56F 4108 \
  62CD FA35 E365 0736 A011 7833 8B35 7BFF DAD8 34A8 452F 2EB4"
INCREMENT 54600ACD_2008_0F adskflex 1.000 permanent 3 \
  VENDOR_STRING=commercial:permanent BORROW=4320 SUPERSEDE \
  DUP_GROUP=UH ISSUED=09-Jan-2008 SN=123-12345678 SIGN="1E6E \
  4B61 5712 4766 92A0 6782 9EF4 3F47 56A1 1F38 6DE8 C0C7 90AC \
  7289 152E 0EA2 CC0D 3F10 577A 0489 CEB6 10D5 FBCC B552 0C9D \
  5966 91A6 59F0 2788 FACE" SIGN2="1DDF 3B9D 3392 71D5 AB08 7E05 \
  8497 111E 092F 0E54 8DC2 2BED 17C2 2CC1 981B 0EC2 BC15 8F00 \
  C79A ABFD 2136 BABA 2EDF E941 EA53 32C6 597F F805 5A8A 599A"
```

Example of Additional Parameters in a License File

For Autodesk products that are included in a product set and are also sold as an individual product, licenses are allocated based on a sequence of priorities defined in the license file. For those products, information similar to the following example appears in a license file:

```
SERVER Server1 1a34567c90d2
USE_SERVER
VENDOR adskflex port=2080
INCREMENT 54600ACD_2008_0F adskflex 1.000 permanent 5 \
  VENDOR_STRING=commercial:permanent BORROW=4320 SUPERSEDE \
  DUP_GROUP=UH ISSUED=09-Jan-2007 SN=123-12345678 SIGN="0247 \
  45D6 87C4 27A5 7F9E F24A ED3D 61E4 6B3B CC5C AD77 B865 9EA8 \
  3D62 0792 0F67 19E7 57E7 FAFA A48B D582 335A EC16 1FE5 B70D \
  76AB 6488 61CC DE5E F5B7" SIGN2="09FD 0850 7CF1 F447 9F05 9FA3 \
  2A0A 38D6 83FC 1746 F3F5 5A72 6250 E002 DE0B 0E6E F88C AC95 \
  136F 87F2 A945 E4C4 A97F 44B5 74EE 83F3 3F3E 1579 B981 8994"
```

License Types and Behaviors

Autodesk supports dynamic product usage and license behaviors. This means that you can purchase a specific type of behavior with a specific license and change that license at a later date without having to uninstall and reinstall the Autodesk product.

NOTE All license types are available as stand-alone and network except for the Student Portfolio license, which is available as stand-alone only.

License types include the following:

- **Commercial.** A license for a product that was purchased commercially.
- **Not for Resale.** A license for a product that is not sold commercially. Not for Resale products are for evaluation or demonstration purposes only and may not be used for commercial or production use.
- **Educational (EDU)/Institution.** A license designed specifically for educational institutions.
- **Student Portfolio.** A license for students who are using an Autodesk product as part of their curriculum.

License behaviors are as follows:

- **Permanent.** Enables permanent use of an Autodesk product.
- **Term Extendable.** Enables access to an Autodesk product for a limited time. The term can be extended at any time.
- **Term Non-Extendable.** Enables an Autodesk product for a limited time. The term cannot be extended.

Heartbeat Signal

When an Autodesk product is running, it communicates with the license server at regular intervals using a communication method known as the “heartbeat” signal. If the heartbeat signal is lost, the server tries to reconnect. If the server cannot reconnect, the user receives a license error.

If the product stops working because it has lost a connection to the server, you must shut down the product, and then restart it. If the problem causing the original loss of the heartbeat signal is resolved and there are available licenses on the server, the program can be restarted.

Network License Manager

Install the Network License Manager

You can install the Network License Manager before or after you use the Installation wizard. The order in which you install the network applications does not matter, as long as you install everything you need and you provide consistent license server information across the network applications.

If an earlier version of the Network License Manager is already installed on the computer, you should upgrade by installing the Autodesk Network License Manager into the folder where the older version was located.

Install the Network License Manager (Mac OS X)

To install the network license manager on Mac OS X:

- 1 Locate the Smoke installation media.
- 2 Open the Standalone Installers folder.
- 3 Start the Install License Server installation.
- 4 Follow the on-screen instructions to complete the installation.

Install the Network License Manager (Linux)

To install the network license manager (Linux):

- 1 Locate the Standalone Installer folder on the Smoke installation media.
- 2 Copy the Burn folder to a Linux machine.
- 3 Log in as root.
- 4 Unzip the tar file. Type:

```
tar -xzvf Burn_*.tar.gz
```
- 5 Open the Burn folder created when you unzipped the package.
- 6 Install Burn. Type:

```
./INSTALL_LICSERV
```

Follow the instructions in to complete the installation.

Obtain a License Through autodesk.com

You can register and activate your network license by going to <https://registeronce.autodesk.com> and following the on-screen instructions.

Obtain the Server Host Name and Host ID Manually

Autodesk uses the server host name, host ID, and product serial number to generate a license file.

To obtain the information manually, you can use the command prompt or you can run the *lmttools.exe* utility. If you use *lmttools.exe*, do not run it on a remote workstation.

To obtain the host name and ID using the Windows command prompt

- 1 Do the following:
 - (Windows XP/Windows Vista) Click Start ► All Programs ► Autodesk ► [Autodesk Product] ► License Transfer Utility.
- 2 At the Windows command prompt, enter the following command, and then press ENTER:
ipconfig /all
- 3 Locate the Host Name line, and write down the host name.
- 4 Locate the Physical Address line. Write down the physical address *without* the dashes. This is your twelve-character host ID.

NOTE If your server has more than one network adapter, select the one that corresponds to a physical network adapter. To determine which adapters are physical: in the Windows command prompt, enter **ipconfig /all**, and then view the Description field above each physical address. If there is more than one physical network adapter, it does not matter which one you use. Devices such as VPN adapters, PPP adapters, and modems are not valid.

- 5 Close the Windows command prompt.

To obtain the host name and ID using lmttools.exe

You should be logged in with Administrator rights when working with the LMTOOLS utility.

- 1 Click Start ► All Programs ► Autodesk ► Network License Manager ► LMTOOLS Utility.
- 2 In the LMTOOLS program, click the Systems Settings tab.
- 3 On the Systems Settings tab, locate the Computer/Hostname box. Copy the host name and paste the information into a text editor.
- 4 Locate the Ethernet Address box. The Ethernet address is the host ID. It consists of twelve characters. Write down the information. If your Ethernet address is more than twelve characters, write down the first twelve characters only.

NOTE If your server has more than one Ethernet adapter, select one that corresponds to a physical network adapter.

- 5 Close *lmtools.exe*.

To obtain the host name and ID using the Mac OS X or Linux terminal window

- 1 Launch a Terminal window.
- 2 Go to the directory where *lmutil* is installed.
- 3 Retrieve the host name by entering the following in Terminal:

```
<prompt>./lmutil lmhostid -hostname
```

The host name is displayed.
- 4 Retrieve the host ID by entering the following in Terminal:

```
<prompt>./lmutil lmhostid
```

The twelve-character host ID is displayed.
- 5 Close the Terminal Window.

Creating Your License File (Linux)

If you are using a Linux Network License Manager, you must save the license file you receive from Autodesk in the following location: */opt/flexnetserver/adsk_server.lic*

Uninstall the Network License Manager

You can uninstall the Network License Manager from the license server. When you uninstall the Network License Manager, licenses are no longer available to your users.

To uninstall the Network License Manager

- 1 Click Start ► All Programs ► Autodesk ► Network License Manager ► LMTOOLS Utility.
- 2 In the LMTOOLS program, click the Start/Stop/Reread tab.
- 3 On the Start/Stop/Reread tab, click Stop Server.
- 4 Close *lmtools.exe*.
- 5 In the Windows Control Panel, do one of the following:
 - (Windows XP) Double-click Add/Remove Programs.
 - (Windows 7/Windows Vista) Double-click Programs and Features.

Do one of the following:

- (Windows XP) In the Add/Remove Programs window, click Autodesk Network License Manager. Click Remove.
- (Windows 7/Windows Vista) In the Programs and Features window, click Autodesk Network License Manager. Click Remove.

6 If prompted, restart your computer.

NOTE You must manually delete files that you created for use with the Network License Manager (such as log files, license files, and the Options file). They are not automatically deleted when you uninstall the Network License Manager.

Network Licensing Tools

Autodesk Network licensing tools include FLEXnet configuration tools, license borrowing, and SAMreport-Lite. Each tool is described in the sections that follow.

This section also includes information for updating FLEXnet and installing and configuring the Autodesk Network License Manager on a network.

FLEXnet Configuration Tools

The Network License Manager uses FLEXnet® license management technology from Acreoso Software. FLEXnet provides administrative tools that help to simplify management of network licenses. You can use FLEXnet tools to monitor network license status, reset licenses lost to a system failure, troubleshoot license servers, and update existing license files on the fly.

Utilities for License Server Management

FLEXnet provides two utilities for managing the license server. These tools are located in the *C:\Program Files\Autodesk Network License Manager* folder.

lmtools.exe Provides a Microsoft® Windows graphical user interface for managing the license server.

lmutil.exe Provides a set of command line options for managing the license server.

You can use *lmtools.exe* or *lmutil.exe* to perform the following server management tasks:

- Start, stop, and restart the server.
- Configure, update, and reread the license file.
- Diagnose system or license problems.
- View server status, including active license status.


Stop and Restart the License Server

Before you can perform any system maintenance on your license server, you must stop the license server. When you have completed maintenance, you can restart the license server.

To restart the license server (Mac OS X)

To restart the license server:

- 1 Open the License Server Configurator. You can find the License Server Configurator in one of the following places:
 - If Smoke is installed on the same workstation: *Applications/Smoke 2011/Utilities*
 - If Smoke is not installed on the workstation: */Applications/Autodesk/Adlm*



- 2 Do one of the following:
 - If the server is not running, click Start.
 - If the server is running, click Restart.

To restart the license server (Linux)

Enter the following in Terminal:

```
/etc/init.d/license_server_adlm stop  
  
/etc/init.d/license_server_adlm restart
```

License Borrowing

If you are running a network-licensed version of the program, you can borrow a license from a license server to use the program for a specified time when your computer is not connected to the network.

NOTE If you have a stand-alone version of the program, you cannot borrow a license. To check your license type, click Help menu ► About ► Product Information. In the Product Information dialog box, view your product license type.

Overview

If you are using a network-licensed version of your Autodesk product and your network administrator supports the license borrowing feature, you can borrow a product license from your network license server to use the program when your computer is not connected to the network. Your license is automatically

returned to the license server at the end of the day on the return date you set when you borrowed the license. You can also return a license early.

NOTE There is a limit to the number of licenses available for borrowing. If you try to borrow a license and are notified that no licenses are available, all network licenses may already be borrowed by other users. If you are unable to borrow a license, see your network administrator for help.

Borrow a License

You can run the program when your computer is not connected to the network until your license-borrowing period ends. If you don't remember the date that a license expires, you can check the date by placing your cursor over the Borrowing icon in the program's status tray or by clicking Help ► About and using the Product Information dialog box.

When the license-borrowing period expires, the borrowed license is automatically returned to the license server. Once your computer is reconnected to the network, you can run the program from the network or borrow a license again.

Interaction with Other License-Borrowing Tools

Using the license borrowing feature in the program is the recommended way to borrow a license; however, some third-party borrowing tools may also be available to you. These tools are not supported or compatible with the license borrowing feature in the program. Other third-party or legacy license-borrowing tools that may be available to you are the Autodesk License Borrowing utility (shipped with Autodesk products) and the borrowing feature in *lmtools.exe*, a component of the Autodesk Network License Manager.

If another license-borrowing tool is active when you attempt to use the license borrowing feature, you should proceed as follows to borrow a license for the program:

- If you run the Autodesk License Borrowing utility that shipped with your Autodesk product and then turn on the borrowing flag for the Adskflex option or the All option, a license can be borrowed when you start the program. However, you cannot return a license until you exit and then restart the program.
- If borrowing is set in *lmtools.exe* for *all* products, you can either (a) use the other tool to borrow licenses for the program or (b) stop the borrowing process in *lmtools.exe* and then use the license borrowing feature in the program.
- If borrowing is set in *lmtools.exe* for non-Autodesk products only, you must stop the borrowing process in *lmtools.exe*. You can then use the license borrowing feature to borrow licenses for your Autodesk product. If you do not stop the borrowing process in *lmtools.exe*, the license borrowing feature will not function.

To borrow a license using the Tools menu

- 1 Click Tools menu ► License Borrowing ► Borrow License.
- 2 In the Borrow a License window, on the calendar, click the date when you want to return the license. This date must be within the valid date range set by your network administrator. The valid date range is displayed in this window.
- 3 Click Borrow License.
- 4 In the License Borrowed message, click OK. The license is borrowed, and you can now use the program while your computer is disconnected from the network.

NOTE You can verify that your license is borrowed by placing your cursor over the Borrowing icon in the status tray, which is in the lower-right corner of the program.

To borrow a license using the Help menu

- 1 Click Help menu ► About.
- 2 In the About product window, click Product Information.
- 3 In the Product Information window, click Borrow License.
- 4 In the Borrow a License window, on the calendar, click the date when you want to return the license. This date must be within the valid date range set by your network administrator. The valid date range is displayed in this window.
- 5 Click Borrow License.
- 6 In the License Borrowed message, click OK. The license is borrowed, and you can now use the program while your computer is disconnected from the network.

BORROWLICENSE Command

Borrows a product license so that you can run the product outside the network environment.

Tools menu: License Borrowing ► Borrow License

Help menu: About ► Product Information ► Borrow License

Command line: **borrowlicense**

The [Borrow a License Window](#) on page 66 is displayed.

Borrow a License Window

Tools menu: License Borrowing ► Borrow License

Help menu: About ► Product Information ► Borrow License

Command line: **borrowlicense**

Using the license borrowing feature, you can borrow a license from your network license server, and then use the license when your computer is disconnected from the license server; for example, when you are traveling for work.

The Borrow a License window has the following options:

Calendar Sets the date when you plan to return a borrowed license. The return date must be within the range specified by your network administrator.

Borrow a License Borrows the license from the network license server based on the return date that you specified.

Cancel Cancels the borrowing action; no license is borrowed.

Return a License

Your network license is automatically returned to the network license server on the day that the license expires. You can also return a license earlier than the date you originally selected, as long as your computer is connected to the network license server when you attempt to return the borrowed license.

Once a borrowed license is returned, you can borrow a license again as long as your computer is connected to the network license server and a license is available on the server.

To return a borrowed license early, do one of the following:

- Click Tools menu ► License Borrowing ► Return License Early.
- Click Help menu ► About ► Product Information. In the Product Information dialog box, click Return License, and then click Yes.
- In the status tray, right-click the License Borrowing icon. Click Return License Early.

NOTE To use the status tray to return a borrowed license early, the display settings for the status tray must be turned on. To turn on the display settings, right-click an empty area on the status bar. Click Tray Settings.

Your license is returned to the network license server. After you return the borrowed license, you can borrow a license again immediately as long as a license for that product is available on the network.

To check the license return date, do one of the following:

- In the status tray, right-click the License Borrowing icon. View the expiration date for the borrowed license.
- Click Help menu ► About ► Product Information. In the Product Information dialog box, under License Expiration Date, view the license return date.

RETURNLICENSE Command

Returns a borrowed Autodesk product license earlier than the original return date that you specified when you borrowed the license.

Tools menu: License Borrowing ► Return License

Help menu: About ► Product Information ► Return License

Status tray: Right-click the License Borrowing icon. Click Return License Early.

Command line: **returnlicense**

Stand-Alone Licensing

B

Topics in this chapter:

- [Introduction](#) on page 69
- [Activate Your Product](#) on page 70
- [Register Your Product](#) on page 70
- [Manage Your Stand-Alone License](#) on page 70
- [Transfer Your Stand-Alone License](#) on page 72
- [Troubleshoot a Stand-Alone License Error](#) on page 72

Introduction

NOTE Standalone licensing is only available for the student edition of Smoke. The commercial edition requires network licensing.

Stand-alone licensing allows you to use your Autodesk product in trial mode for a given number of days from the first time you launch the product. The number of days that a trial mode is active differs between Autodesk products. You can activate your license at any time before the trial period expires.

When you activate your product, you receive an activation code. If you activate online, your activation code is automatically retrieved from Autodesk and the product starts. Activations are also available through email, fax, phone, or the Autodesk website.

NOTE If you are installing and using an Autodesk product on both operating systems of a dual-boot operating system, you must obtain a separate activation code for each operating system.

The license file stays on your workstation when you uninstall your product. If you reinstall your Autodesk product on the same workstation, the license information is still valid. You do not have to reactivate the product.

Multi-Seat Stand-Alone License

A multi-seat stand-alone license allows you to install, register, and activate an Autodesk product on several workstations using a single serial number. Multi-seat licenses can be purchased through your Authorized Autodesk Reseller.

NOTE Multi-seat standalone licensing is only available for the student edition of Smoke.

Activate Your Product

You can activate your Autodesk product either on startup or while you are running the product. If you cannot activate online, offline activation is available.

Register Your Product

Depending on your product, registration is optional or required. If required, you are asked to create a user Autodesk ID and associate this ID with an individual or company account. If registration is optional, you can choose to postpone it, and you will be reminded periodically to register.

Manage Your Stand-Alone License

This section provides information about advanced stand-alone licensing tasks such as license types and behaviors, viewing product information, saving your license file as a text file, updating your serial number, and transferring a license.

Check Product Information

You can view detailed information about your Autodesk product and your product license (such as the license usage type and the license behavior), and then save this information as a text file.

License usage types

NOTE All license types are available as stand-alone and network except for the Student Portfolio license, which is available as stand-alone only.

Commercial A license for a product that was purchased commercially.

Not for Resale A license for a product that is not sold commercially.

Educational (EDU)/Institution A license designed specifically for educational institutions.

Student Portfolio A license for students who are using an Autodesk product as part of their curriculum.

License behaviors

Trial A license that allows individuals to try the product in trial mode for a specified number of days. The trial period starts the first time you launch your product. When the trial period expires, the product must be registered and activated to continue use.

Permanent Allows permanent use of an Autodesk product.

Term Extendable Allows access to an Autodesk product for a limited time. The term can be extended at any time.

Term Non-Extendable Allows access to an Autodesk product for a limited time. The term cannot be extended.

View Product Information

You can view detailed information about your Autodesk product and your product license, such as the license usage type and the license behavior.

To view product information

- 1 Launch your Autodesk product.
- 2 On the Help menu, click About.
- 3 In the About *[Autodesk Product]* window, click Product Information.
- 4 In the Product Information dialog box, view details about your product and the product license.
- 5 In the Product Information dialog box, click Close.

Save License Information as a Text File

You can save your product license information as a text file.

To save license information as a text file

- 1 Launch your Autodesk product.
- 2 On the Help menu, click About.
- 3 In the About *[Autodesk Product]* window, click Product Information.
- 4 In the Product Information dialog box, click Save As.
- 5 In the Save As dialog box, name the file, choose a location where you want to save the file, and then click Save.
- 6 In the Product Information dialog box, click Close.

Update Your Serial Number

Your valid serial number is located on the outside of the product packaging or in the *Autodesk Upgrade and Licensing Information* email you received if you downloaded your product.

When you register and activate your product, you are asked for the product serial number, which is automatically entered upon completion of the activation process.

If you have a multi-product bundle of software that uses a single serial number, only the first product you register and activate displays the updated serial number. For other products to display the serial number, you must update it from the Help menu.

NOTE For the updated serial number to display, you must be logged into the system with Administrator rights.

To update your serial number

- 1 Launch your Autodesk product.
- 2 On the Help menu, click About.
- 3 In the About *[Autodesk Product]* window, click Product Information.
- 4 In the Product Information dialog box, click Update.
- 5 In the Update the Serial Number dialog box, enter your product serial number.

The serial number is located on the outside of the product packaging or in the *Autodesk Upgrade and Licensing Information* email you received if you downloaded your product.

NOTE If you have lost your serial number, contact the Autodesk Business Center (ABC) at 800-538-6401 for assistance.

- 6 Click OK. You can now see the updated serial number.

Transfer Your Stand-Alone License

About the Licence Transfer Utility

Install the Autodesk Product

Export a License

Import a License

Troubleshoot a Stand-Alone License Error

When you activate your Autodesk product, only the computer that you used to activate the product is licensed to run the product. If you make certain changes to your computer, your stand-alone license might fail. You will receive a license error and you will not be able to use your product. This section discusses ways in which you can troubleshoot a license error.

Some license errors require you to reactivate your product. If you need to reactivate your product, the Product Activation wizard is displayed when you try to run the product. To reactivate your product, follow the instructions in the Product Activation wizard.

The following topics offer more details regarding specific errors.

Hardware Changes

If you replace or reconfigure hardware on the computer where your Autodesk product license resides, the stand-alone license might fail. You will not be able to use your product.

To prevent damage to your product license, use the License Transfer Utility to export your license file. After you make the hardware change, you can import the license file back. For instructions about using the License Transfer Utility, see [Transfer Your Stand-Alone License](#).

NOTE If you get a license error when you change your hardware, you may have to reactivate your license. See [Activate Your Product](#) on page 70.

Reinstalling an Operating System

If you reinstall your operating system on the computer where your Autodesk license resides, the license might fail. You will not be able to use your product.

To resolve a license error in this case, you must reactivate your product. See [Activate Your Product](#) on page 70.

To prevent a license error when you reinstall an operating system

NOTE If using Norton Ghost™ or another image utility, do not include the Master Boot Record.

- 1 Locate one of the following folders and make a backup copy:
 - (Windows XP) C:\Documents And Settings\All Users\Application Data\FLEXnet
 - (Windows 7/Windows Vista) C:\ProgramData\FLEXnet
- 2 Reinstall the operating system and reinstall the Autodesk product.
- 3 Paste the license folder to the same location from which you originally copied the folder in step 1. You can now run your Autodesk product.

Changing the System Date and Time

Your product license allows for time changes to the system clock within two days of the current time. If you set your system clock back more than two days, the next time you start your product, you will receive a message that gives you the option of correcting the system clock. If you do not correct the system clock, you receive a license error.

To prevent a license error due to a change in system date and time

- Make sure that your computer's system date and time are accurate when you install and activate your Autodesk product.

Distributing Software Image to Multiple Computers

You can use the Deployment Wizard's Stand-alone option to create a software installation image on your server. You can distribute this image by making it available on your computer network. During creation of this image, you are prompted for registration information, which is stored with the image and deployed to all installations.

Additionally, you can manually distribute the software using the installation CD that comes with your Autodesk product. However, if your computers do not have an Internet connection, make sure the registration data for each computer matches exactly. Inconsistent registration data can cause activation failures.

To prevent a license error when distributing software image to multiple computers

- The distribution of applications using "ghosting" is not recommended, and can result in incomplete installations and activation problems.

Preserving Licenses on Re-Imaged Computers

On a network license server, licenses are maintained on the server. No additional steps are needed to preserve network licenses.

For stand-alone licenses, you need to export the licenses to a safe place before re-imaging the computers. You can use the License Transfer Utility to export the licenses. After the re-imaging, import the licenses to the correct computer. Each license only works on the computer for which it was created.

Licensing Glossary



Topics in this chapter:

- [Glossary](#) on page 75

Glossary

ADSKFLEX_LICENSE_FILE In a distributed license server configuration, the environment variable used to point a workstation to the distributed license servers.

adskflex.exe The Autodesk vendor daemon used with the FLEXnet license technology. This daemon keeps track of the Autodesk licenses that are checked out and the workstations that are using the licenses.

borrowed license A license that allows you to use an Autodesk product for a limited period of time without having to buy a separate license or have network access to the license server.

daemon A program that runs continuously in the background of a computer. The daemon handles requests from the computer and then forwards the requests to other programs or processes. The Network License Manager uses two daemons: the vendor daemon (*adskflex.exe*) and the license manager daemon (*lmgrd.exe*).

debug log file A file used with FLEXnet to log connection activity (such as license failure or starting and stopping) between the Network License Manager and the workstation.

deployment The files and folders created on a server and used by workstations to install Autodesk programs.

distributed server A license server configuration option in which several servers are used to manage license distribution. Each distributed license server has a unique license file and a fixed number of licenses. If one distributed license server fails, the other servers are still able to distribute their licenses.

Ethernet address See *host ID*.

feature code A license file parameter that represents the product that is supported by that license file.

FLEXnet The Acreoso Software license management technology implemented in the Autodesk family of products.

heartbeat signal The communication signal between the Network License Manager and the workstation to verify that the workstation is accessible and has an active Autodesk product session running.

host ID The unique hardware address of a network adapter. Also known as *Ethernet address* or *physical address*.

host name The TCP/IP name associated with a computer. FLEXnet technology uses the host name as a parameter; the host name must be distinguished from the NetBIOS (server) name.

idle A state of inactivity in your product that prompts a network license server to reclaim a license. Inactivity is due to no mouse or keyboard activity and no commands, LISP expressions, menu macros, or scripts in progress for the period of time that is defined in the Options file. See also *license timeout*.

JRE (Java Runtime Environment) A program that is required to run Java programs. This program must be installed with SAMreport-Lite.

license file A file used with FLEXnet that controls the number of available seats. This file must be in ASCII plain text format.

license server A server that contains the Network License Manager.

license timeout A feature that allows you to set up a timeout period on your license server to automatically return an idle license to the server so that it is available for use again.

licpath.lic In both single and redundant server configurations, the file used to point the workstation to the FLEXnet license server. *Licpath.lic* is located in the root installation folder.

lmgrd.exe The license manager daemon. This daemon handles the original contact with the program, and then passes the connection to the vendor daemon, *adskflex.exe*.

lmtools.exe A graphical user interface utility used to administer the FLEXnet license technology. (*Lmutil.exe* is the command line version of this utility.)

lmutil.exe A command line utility used to administer the FLEXnet license technology. (*lmtools.exe* is the graphical user interface version of this utility.)

master daemon See *lmgrd.exe*.

network license installation A type of installation that requires you to install and run the Network License Manager from a network server. You must install and configure the Network License Manager before clients can run the Autodesk product.

Network License Manager The technology used by Autodesk for network license management.

Options file The file used by FLEXnet to control license manager parameters, such as reserving licenses and creating report logs used with SAMreport-Lite.

physical address See *host ID*.

redundant server A license server configuration option in which three servers are used to administer licenses. The redundant servers share a license file and a pool of licenses. The redundant server pool remains functional as long as two of the three servers are running and communicating with each other.

report log file A file used with FLEXnet and SAMreport-Lite. This log file provides information about network license usage. The Options file creates the report log.

SAMreport-Lite A version of Acrecco Software's SAMreport tool. SAMreport-Lite is included on the Autodesk product discs.

vendor daemon See *adskflex.exe*.

workstation A desktop computer used by an individual user on a network.

Index

A

- activating programs 70
- Adskflex option 65
- adskflex.exe (Autodesk vendor daemon) 56
- Autodesk License Borrowing utility 65
- Autodesk Network License Manager 65
- Autodesk products
 - activating 70
 - borrowing network licenses for 64
 - reinstalling 73
 - using off network 64

B

- borrowing licenses
 - about 64
 - reconnecting and borrowing again 65–66
 - returning licenses 66
- borrowing periods 65
- BORROWLICENSE command
 - about 66

C

- Commercial licenses 60, 70
- compatibility
 - transferring media from previous versions 38
- computers
 - re-imaged 73
- copying
 - licenses 72
- customer support
 - contacting 2

D

- daemons
 - license manager daemons 56
 - vendor daemons 56
- dates
 - expiration 65
 - system dates 73
- Deployment wizard 73
- DHCP 41
- displaying
 - product license information 71
- distributed license server model
 - about 54

- license file example 58
- distributing
 - software installation images 73
- documentation
 - conventions 1
- documentation for this release 2

E

- early returns of licenses 66
- Educational (EDU)/Institution licenses 60, 70
- email registration 24
- Ethernet address 61
- expiration dates for licenses
 - about 65

F

- fax registration 24
- FLEXnet tools
 - about 63

G

- glossary 76

H

- hardware
 - license errors and 72
- hardware requirements
 - Network License Manager 51, 53
- heartbeat signals 60
- host IDs 61
- host names 61

I

- Imtools.exe 65
- installation
 - Network License Manager 60

L

- license borrowing
 - about 64
 - borrowing licenses 64–65
 - expiration dates 65

- returning licenses 66
 - third-party licensing tools 65
- license files
 - about 56
 - additional parameters in 59
 - combined products 59
 - examples 57
- license manager daemon 56
- license server
 - troubleshooting 40
- license servers
 - borrowing licenses 64–65
 - heartbeat signals 60
 - host IDs and host names 61
 - installing on Mac OS X 60
 - limited number of licenses 65
 - management utilities 63
 - models 54
 - returning licenses 66
 - stopping and restarting 63
 - third-party licensing tools 65
 - types of 54
- licenses
 - about 55
 - assigning 55
 - availability 55
 - behaviors (term limits) 60
 - copying 72
 - FLEXnet tools 63
 - glossary 76
 - license errors 72
 - license files 56
 - moving between computers 72
 - single-user 69
 - troubleshooting 72
 - types of 60
- licensing
 - DHCP 41
- limits on number of licenses 65
- Linux
 - Network License Manager 53
- lmgrd.exe (license manager daemon) 56
- lmtools.exe utility 61, 63
- lmutil.exe utility 63

M

- Mac OS X
 - installing license server 60
 - Network License Manager 53
- Microsoft Windows
 - Network License Manager 51

N

- network license installations
 - planning 51
 - tools and utilities 63
 - types of 60

- Network License Manager
 - assigning licenses 55
 - glossary 76
 - installing 60
 - license server models 54
 - uninstalling 62
 - upgrading 60
- network license servers
 - borrowing licenses 64–65
 - limited number of licenses 65
 - returning licenses 66
 - third-party licensing tools 65
- Not for Resale licenses 60, 70

O

- offline registration 24
- operating systems
 - reinstalling 73
- OS X
 - Network License Manager 53

P

- parameters in license files 59
- periods for licenses
 - about 65
- Permanent licenses 60, 70
- physical address 61
- Product Activation wizard 72

R

- re-imaged computers 73
- reactivating programs 72
- redundant license server model
 - about 55
 - license file example 58
- registering
 - offline 24
- registering programs 70
- reinstalling
 - operating systems 73
- return dates for licenses
 - about 65
- returning borrowed licenses 65–66
- RETURNLICENSE command 67

S

- serial numbers
 - updating 71
- servers
 - host IDs and host names 61
 - stopping and restarting 63
- single license server model
 - about 54
 - license file example 58

- single-user licenses 69
- software requirements
 - Network License Manager 51, 53
- stand-alone licenses 69
- Student Portfolio licenses 60, 70
- support
 - contacting 2
- system dates 73
- system requirements
 - Network License Manager 51, 53
- system times 73

T

- TCP/IP names 61
- Term Extendable licenses 60, 70
- Term Non-Extendable licenses 60, 70
- third-party licensing tools 65
- time
 - system time 73
- time periods for licenses
 - about 65

- Trial licenses 70
- troubleshooting
 - license server status 40
- troubleshooting license errors 72

U

- uninstalling
 - Network License Manager 62
- upgrading
 - Network License Manager 60

V

- vendor daemons 56

W

- Windows
 - Network License Manager 51

