

**Autodesk®**  
Backburner™ 2010.1

# User Guide

© 2009 Autodesk, Inc. All rights reserved. Except as otherwise permitted by Autodesk, Inc., this publication, or parts thereof, may not be reproduced in any form, by any method, for any purpose.

Certain materials included in this publication are reprinted with the permission of the copyright holder.

Portions relating to MD5 Copyright (C) 1991-2, RSA Data Security, Inc. Created 1991. All rights reserved. License to copy and use this software is granted provided that it is identified as the "RSA Data Security, Inc. MD5 Message-Digest Algorithm" in all material mentioning or referencing this software or this function. License is also granted to make and use derivative works provided that such works are identified as "derived from the RSA Data Security, Inc. MD5 Message-Digest Algorithm" in all material mentioning or referencing the derived work. RSA Data Security, Inc. makes no representations concerning either the merchantability of this software or the suitability of this software for any particular purpose. It is provided "as is" without express or implied warranty of any kind. These notices must be retained in any copies of any part of this documentation and/or software.

The following are registered trademarks or trademarks of Autodesk, Inc., and/or its subsidiaries and/or affiliates in the USA and other countries: 3DEC (design/logo), 3December, 3December.com, 3ds Max, ADI, Algor, Alias, Alias (swirl design/logo), AliasStudio, Alias|Wavefront (design/logo), ATC, AUGI, AutoCAD, AutoCAD Learning Assistance, AutoCAD LT, AutoCAD Simulator, AutoCAD SQL Extension, AutoCAD SQL Interface, Autodesk, Autodesk Envision, Autodesk Intent, Autodesk Inventor, Autodesk Map, Autodesk MapGuide, Autodesk Streamline, AutoLISP, AutoSnap, AutoSketch, AutoTrack, Backburner, Backdraft, Built with ObjectARX (logo), Burn, Buzzsaw, CAiCE, Can You Imagine, Character Studio, Cinestream, Civil 3D, Cleaner, Cleaner Central, ClearScale, Colour Warper, Combustion, Communication Specification, Constructware, Content Explorer, Create>what's>Next> (design/logo), Dancing Baby (image), DesignCenter, Design Doctor, Designer's Toolkit, DesignKids, DesignProf, DesignServer, DesignStudio, Design|Studio (design/logo), Design Web Format, Discreet, DWF, DWG, DWG (logo), DWG Extreme, DWG TrueConvert, DWG TrueView, DXF, Ecotect, Exposure, Extending the Design Team, Face Robot, FBX, Fempro, Filmbox, Fire, Flame, Flint, FMDesktop, Freewheel, Frost, GDX Driver, Gmax, Green Building Studio, Heads-up Design, Heidi, HumanIK, IDEA Server, i-drop, ImageModeler, iMOUT, Incinerator, Inferno, Inventor, Inventor LT, Kaydara, Kaydara (design/logo), Kynapse, Kynogon, LandXplorer, Lustre, MatchMover, Maya, Mechanical Desktop, Moldflow, Moonbox, MotionBuilder, Movimento, MPA, MPA (design/logo), Moldflow Plastics Advisers, MPI, Moldflow Plastics Insight, MPX, MPX (design/logo), Moldflow Plastics Xpert, Mudbox, Multi-Master Editing, NavisWorks, ObjectARX, ObjectDBX, Open Reality, Opticore, Opticore Opus, Pipeplus, PolarSnap, PortfolioWall, Powered with Autodesk Technology, Productstream, ProjectPoint, ProMaterials, RasterDWG, Reactor, RealDWG, Real-time Roto, REALVIZ, Recognize, Render Queue, Retimer.Reveal, Revit, Showcase, ShowMotion, SketchBook, Smoke, Softimage, Softimage|XSI (design/logo), Sparks, SteeringWheels, Stitcher, Stone, StudioTools, Topobase, Toxik, TrustedDWG, ViewCube, Visual, Visual Construction, Visual Drainage, Visual Landscape, Visual Survey, Visual Toolbox, Visual LISP, Voice Reality, Volo, Vtour, Wire, Wiretap, WiretapCentral, XSI, and XSI (design/logo).

Adobe, Flash and Reader are either trademarks or registered trademarks in the United States and/or countries. Automatic Duck and the duck logo are trademarks of Automatic Duck, Inc. FFmpeg is a trademark of Fabrice Bellard, originator of the FFmpeg project. Python is a registered trademark of Python Software Foundation. All other brand names, product names or trademarks belong to their respective holders.

## Disclaimer

THIS PUBLICATION AND THE INFORMATION CONTAINED HEREIN IS MADE AVAILABLE BY AUTODESK, INC. "AS IS." AUTODESK, INC. DISCLAIMS ALL WARRANTIES, EITHER EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE REGARDING THESE MATERIALS.

Published by:

Autodesk, Inc.

111 McInnis Parkway

San Rafael, CA 94903, USA

Images courtesy of: Duckling, Absolute Post, Finish

Title: Autodesk Backburner 2010.1 User Guide

Document Version: 1

Date: August 26, 2009

# contents

---

## Contents

## Section 1 Preparation

<b>1</b>	<b>Introduction</b>	<b>3</b>
	Summary .....	3
	Welcome to Backburner .....	3
	Backburner Terminology .....	4
	Backburner Architecture .....	6
	Notation Conventions .....	7
	Related Documentation .....	7
	Contacting Customer Support .....	7
<b>2</b>	<b>Getting Started</b>	<b>9</b>
	Summary .....	9
	Overview .....	9
	Backburner Windows Monitor .....	11
	Backburner Web Monitor .....	16
	WiretapCentral Backburner Monitor .....	19
	Working with Jobs .....	21
	Working with Render Nodes .....	24

## Section 2 Backburner Windows Monitor Reference

<b>3</b>	<b>Managing and Modifying Jobs – Windows</b>	<b>31</b>
	Summary .....	31
	Overview.....	31
	Finding and Monitoring Jobs .....	32
	Customizing the Job List .....	33
	Suspending and Reactivating Jobs.....	34
	Modifying Job Settings.....	35
	Restarting Jobs.....	38
	Cloning Jobs.....	38
	Archiving Jobs .....	39
	Deleting Jobs .....	40
<b>4</b>	<b>Managing Render Nodes – Windows</b>	<b>43</b>
	Summary .....	43
	Overview.....	43
	Monitoring Render Nodes .....	44
	Customizing the Render Node List .....	46
	Shifting Nodes Between Jobs.....	47
	Deleting Offline Render Nodes.....	48
	Setting Render Node Availability.....	48
	Working with Server Groups .....	49

## Section 3 Backburner Web Monitor Reference

<b>5</b>	<b>Managing and Modifying Jobs – Web</b>	<b>55</b>
	Summary .....	55
	Overview.....	55

	Finding and Monitoring Jobs . . . . .	55
	Suspending and Reactivating Jobs . . . . .	59
	Modifying Job Settings . . . . .	60
	Restarting Jobs . . . . .	63
	Cloning Jobs . . . . .	63
	Archiving Jobs . . . . .	65
	Deleting Jobs . . . . .	67
<b>6</b>	<b>Managing Render Nodes – Web</b>	<b>69</b>
	Summary . . . . .	69
	Overview . . . . .	69
	Monitoring Render Nodes . . . . .	69
	Shifting Nodes Between Jobs . . . . .	72
	Deleting Offline Render Nodes . . . . .	74
	Setting Render Node Availability . . . . .	75
	Working with Server Groups . . . . .	76
<b>A</b>	<b>Additional Windows Interfaces</b>	<b>81</b>
	Summary . . . . .	81
	Overview . . . . .	81
	Backburner Manager – Windows . . . . .	82
	Backburner Server – Windows . . . . .	82
<b>B</b>	<b>Advanced Operations</b>	<b>83</b>
	Summary . . . . .	83
	Submitting Jobs from a Command Line or Script . . . . .	83
<b>C</b>	<b>Troubleshooting Backburner</b>	<b>87</b>
	Summary . . . . .	87
	Basic Troubleshooting Techniques . . . . .	87
	Common Problems . . . . .	88
	Verifying Communication Between Two Hosts . . . . .	91
	Verifying the Packet Size . . . . .	92
	Configuring Backburner Log Files . . . . .	92
	Editing the backburner.xml File . . . . .	96
	Resolving a Host Access Error . . . . .	97

Resolving Invalid DNS Addresses . . . . .	98
Resolving a Problem Connecting to the Backburner Manager . . . . .	98
Adding the Backburner Path to the Windows Path Environment Variable . . . . .	100
Resolving Network Card Priority . . . . .	101
Resolving an Unavailable Render Node Problem . . . . .	102
Restarting Suspended Render Nodes . . . . .	104
Resolving a Render Node Failure . . . . .	104
Adjusting the Maximum Number of Render Nodes Per Job . . . . .	104

<b>Index</b>	<b>107</b>
--------------	------------

# Section 1

## Preparation

Introduction	3
Getting Started	9



Image courtesy of Duckling



# Introduction

## Summary

<a href="#">Welcome to Backburner</a>	3
<a href="#">Backburner Terminology</a>	4
<a href="#">Backburner Architecture</a>	6
<a href="#">Notation Conventions</a>	7
<a href="#">Related Documentation</a>	7
<a href="#">Contacting Customer Support</a>	7

## Welcome to Backburner

Welcome to the *Autodesk Backburner User Guide*. Backburner™ is the Autodesk® queue manager for background processing and distributed network processing. It provides the means to submit, monitor and control media rendering and I/O jobs.

Backburner is leveraged by the following Autodesk applications:

- |            |           |            |            |          |                      |
|------------|-----------|------------|------------|----------|----------------------|
| • Flint®   | • Flame®  | • Inferno® | • Smoke®   | • Flare™ | • WiretapCentral™    |
| • 3ds Max® | • Lustre® | • Maya®    | • Cleaner® | • Burn®  | • Backdraft® Conform |

This guide relates to using Backburner to monitor and control background processing and distributed network processing. For information on submitting jobs to Backburner from an Autodesk application, refer to the user guide for the application of interest. For information on installation and configuring, refer to the *Autodesk Backburner Installation Guide*.

**NOTE:** This guide documents the Backburner Windows Monitor and Backburner Web Monitor. For information on the WiretapCentral Backburner Monitor, see the *WiretapCentral User Guide*.

## Intended Audience and Prerequisites

This guide is for the person or people responsible for monitoring, managing or maintaining the Backburner network. It is also for anyone interested in the details of how Backburner processes jobs. Whatever your interests, familiarity with the following selected topics will prove helpful:

- The Autodesk application(s) from which jobs will be submitted
- Linux® and/or Windows®
- Computer networking

**NOTE:** If you are new to Backburner, it is recommended that you read the *Backburner Installation Guide* before continuing with this guide. It contains valuable information on a number of key Backburner concepts. This includes the differences between its two main deployment models: the standalone workstation, and the render farm. It also provides details on how Backburner is used by each of the applications that leverages it.

If you require assistance, please contact Autodesk Media and Entertainment customer support. See [“Contacting Customer Support”](#) on page 7.

## Backburner Terminology

Familiarity with following terms will be helpful in understanding the remainder of this guide.

Term	Definition
Backburner	The Autodesk distributed job management system for execution of rendering and I/O jobs in the background.
Job	A set of one or more tasks submitted to Backburner for processing, such as a 3ds Max scene, Flame Batch setup or background I/O job.
Task	The smallest unit of work that can be sent to a render node for processing. This could be a single frame, a portion of a frame, or an entire background I/O job, depending on the job type and the creative application submitting it.
Block	A group of tasks sent to a render node as a unit. For example, when you submit a Burn job from Smoke, each render node normally receives a number of frames for processing at once.
Backburner Manager	Coordinates jobs submitted by creative applications and delegates them to the Backburner servers on the Backburner network.
Backburner Windows Monitor Backburner Web Monitor	Front-end interfaces for management and control of the Backburner Manager.
Backburner Server	The job-processing component of Backburner, residing on each render node, that invokes the local processing engine.

Term	Definition
Adapter	The means by which job-specific processing engines are integrated into Backburner. Sits between the Backburner server and the processing engine.
Processing Engine	The server-side process responsible for carrying out the tasks assigned by the Backburner Manager—rendering animations, scenes and frames, or performing background I/O. A renderer is a particular kind of processing engine.
Server Group	A named collection of Backburner servers.


## Packets, Buckets and Backburner

In other industry literature, the term *packet* is sometimes used to mean the number of frames sent to a render node for processing. A “packet” size of 5, for example, means 5 frames are sent to each available render node. In Backburner, the term *packet* retains its traditional meaning under TCP/IP. In Backburner, the blocks of tasks automatically sent to render nodes for processing are similar to what other software manufacturers call packets.

Similarly, *bucket rendering* is a commonly used term for the concept of explicitly dividing a single image into slices (or tiles), for processing on different render nodes. The same concept applies in Backburner (for 3ds Max), but no particular term is used to describe the process. Backburner simply receives jobs from its render clients, and sends them to the render nodes for processing as blocks of tasks. Whether tasks represent entire frames, or portions of frames, is transparent to its operation.

## Backburner Architecture

As illustrated in the following diagram, Backburner consists of the Backburner Manager, Backburner Monitor, and Backburner Servers. These operate in the greater context of creative applications (such as Autodesk Visual Effects and Finishing applications) and processing engines (such as Burn™).



### Backburner Manager

At the centre of Backburner is the Backburner Manager. It receives jobs from the clients, which it then distributes to the render nodes on the network. The Backburner Manager maintains status information about its network of Backburner servers. It also maintains a database of submitted, active, and, depending on your settings, completed jobs.

### Backburner Monitor

End-user and administrator interaction with the Backburner Manager is by way of the Backburner Monitor. It is used to monitor the progress of a job, suspend and restart jobs, and perform administrative tasks.

## Render Nodes

Render nodes consist of a Backburner Server, adapters and processing engines. The kinds of jobs a render node can process depend on the adapters and processing/rendering engines installed upon it. Autodesk Visual Effects and Finishing applications share the Burn rendering engine and Wire® processing engine. Some Autodesk applications, such as 3ds Max®, have their own rendering engine. Cleaner®, too, provides its own rendering engine. For efficiency, you can group render nodes together in named groups, called *server groups*. Particular jobs can then be processed by the nodes in a named group only, leaving nodes outside the group free for other uses.

## Notation Conventions

A number of style conventions are used throughout this guide. These conventions and examples of their use are shown as follows.

Convention	Example
Text that you enter in a command line appears in Courier bold. You must press the Enter key after each command.	<b>rpm -qa</b>
Variable names appear in Courier, enclosed in angle brackets. No spaces are allowed in variable names.	<variable_name>
Variables that appear enclosed in square brackets are optional.	[<filename>]
Feedback from the command line appears in Courier.	limit coredumpsize
Directory names, filenames, URLs, and command line utilities appear in italics.	<i>/usr/discreet</i>

## Related Documentation

This release has documentation that helps you install, configure, and use the software. The documentation is available from your product DVD, on the Autodesk Web site, and is installed with the product (as PDF files and as an HTML help system).

For a list of all the documentation available to you, visit <http://www.autodesk.com/me-documentation>. From this page you can access the complete documentation library.

You should also refer to your product's release notes for all late-breaking release information.

## Contacting Customer Support

For contact information for Autodesk Media and Entertainment Customer Support, consult your release notes, or visit <http://www.autodesk.com/support>.

Customer support is also available through your Autodesk reseller. To find a reseller near you, consult the reseller look-up database at [\*http://www.autodesk.com/resellers\*](http://www.autodesk.com/resellers).

# Getting Started



## Summary

<a href="#">Overview</a> .....	9
<a href="#">Monitor Comparison</a> .....	10
<a href="#">Backburner Windows Monitor</a> .....	11
<a href="#">Backburner Web Monitor</a> .....	16
<a href="#">WiretapCentral Backburner Monitor</a> .....	19
<a href="#">Working with Jobs</a> .....	21
<a href="#">Working with Render Nodes</a> .....	24

## Overview

As noted in the introduction, end-user and administrator interaction with the Backburner network is mainly by way of the Backburner Monitor. This is the means by which you carry out the daily tasks of observing and controlling jobs and managing render nodes. For jobs, it includes pausing, stopping and restarting jobs, changing job priorities, archiving and restoring jobs, and so on. For render nodes it includes setting render node availability schedules and assigning particular render nodes to jobs. It also includes creating and managing *server groups*—named collections of render nodes that can assist in implementing a job processing strategy, for render farms serving more than one creative application.

**NOTE:** Autodesk applications that leverage Backburner often have basic job queue monitoring abilities built in to the user interface. For more information, see the application-specific User Guide.

The Backburner Monitor is available in three forms:

- **BACKBURNER WINDOWS MONITOR.** A feature-rich UI to the Backburner network. It can be launched from any Windows workstation on the network, and leverages the complete

functionality of the Backburner Manager. This monitor is well-suited for a small render farm with a single creative workstation, or the administrator workstation on a larger render farm.

- **BACKBURNER WEB MONITOR.** Designed for non-administrator workstations on a large render farm, this lightweight monitor allows you to manage jobs and render nodes using any web browser. Its advantages over the Backburner Windows Monitor are two-fold. First, it can run on any workstation with a web browser, rather than a Windows workstation only. Second, it has minimal impact on the Backburner Manager.
- **WIRETAPCENTRAL BACKBURNER MONITOR.** WiretapCentral provides interactive access to media assets on Autodesk Wiretap networks. Its UI is a desktop-like application that runs entirely inside any web browser. The Backburner monitor built in to WiretapCentral is especially designed for tracking the progress of transcoding jobs, when using WiretapCentral with Backburner to import computationally-intensive media formats, such as R3D and OpenEXR files.

The aim of this chapter is to introduce the UIs and general features of the three available monitors, with details on launching them and connecting to a Backburner Manager. It also introduces the main categories of the tasks you can perform: those that are related to jobs, and those for working with render nodes. Details on using the monitors are left for later chapters.

**NOTE:** This guide provides only a brief overview of the WiretapCentral Backburner Monitor. For more information, see the *WiretapCentral User Guide*.

## Monitor Comparison

The following table summarizes the major differences between the monitors.

	Windows Monitor	Web Monitor	WiretapCentral Monitor
Operating System	• Windows OS	• OS independent (browser-based)	• OS independent (browser/Adobe Flash Player-compatible)
Update Mechanism	• Automatic via broadcasts from Backburner Manager	• On demand via end-user requests	• On demand via end-user requests
Control of Job Queue	• Obtained by first monitor to connect to the manager • Also, by request made from a non-controlling monitor	• On demand when changes are requested	• On demand when changes are requested



	Windows Monitor	Web Monitor	WiretapCentral Monitor
User Accounts	<ul style="list-style-type: none"> <li>• Not applicable. All users operate with admin privileges</li> </ul>	<ul style="list-style-type: none"> <li>• User account required to log in to web monitor</li> </ul>	<ul style="list-style-type: none"> <li>• Optional</li> </ul>
Suitability	<ul style="list-style-type: none"> <li>• Small render farm with single creative workstation</li> <li>• Administrator workstation on larger render farm</li> </ul>	<ul style="list-style-type: none"> <li>• Non-administrator workstations on larger render farm</li> </ul>	<ul style="list-style-type: none"> <li>• Monitoring the transcoding of R3D and OpenEXR media</li> </ul>

## Before You Begin

Please note the following general points:


- **USER ACCOUNT AND PASSWORD.** Depending upon how Backburner has been installed and configured, you may need a user account and password to gain access to the chosen monitor.
- **ADMINISTRATOR PRIVILEGES.** Users without administrator privileges can perform operations on the jobs they themselves submit, but can only observe other jobs on the Backburner network. Depending on the monitor used, you may need administrator privileges to actively manage all jobs and render nodes.
- **MANAGER NAME OR IP ADDRESS.** In order to connect the Backburner Monitor to a Backburner Manager, you require the Backburner Manager name, host name, or IP address.

**NOTE:** The above points are dependent on how your Backburner network is set up, and the monitor version in use. For example, the Backburner Windows Monitor automatically acquires administrator privileges when it obtains queue control. No special account is needed.

## Backburner Windows Monitor

The feature-rich Backburner Windows Monitor can be launched from any Windows workstation on the network. It leverages the complete functionality of the Backburner Manager.

## 2 Getting Started




Like the other monitors, the Windows Monitor operates by connecting to a Backburner Manager. The first Windows monitor making the connection has full control over the job queue and Backburner network—that is, “queue control”. Subsequent connections by other Windows Monitors have more limited functionality. See [“Obtaining Queue Control”](#) on page 14.

**NOTE:** Due to the internal updating mechanism, it is suggested you avoid running the Backburner Windows Monitor on more than one or two workstations, since this can degrade network performance. Non-administration workstations can make use of the Backburner Web Monitor instead. For more information, see the *Backburner Installation Guide*.

### To launch the Backburner Windows Monitor:

1. From the Start menu, choose Programs, Autodesk, Backburner, and then Monitor.

The Backburner Monitor appears. If this is your first time running the application, no network or job details are present, since it is not yet connected to a Backburner Manager.




2. Connect to a Backburner Manager. From the Manager menu, choose Connect.
3. In the Connect to Manager dialog that appears, uncheck the *Automatic Search* checkbox, and enter the host name, manager name or IP address of the Backburner Manager in the *Enter Manager Name or IP Address* text field.

Employing automatic searching is not recommended, since it makes extensive use of network resources and can take some time.

4. Click OK to initiate the connection.

The monitor connects to the selected manager, and the UI is populated with job and server details for the Backburner network.



**NOTE:** If the title bar displays “Read Only”, this indicates another user has already connected to the manager via a Backburner Windows Monitor. To perform all common tasks, you will need queue control. See [“Obtaining Queue Control”](#) on page 14.

5. Verify the connection. From the Manager menu, choose Properties.  
Manager details appear in a dialog. If no connection was made, this option is greyed-out.
6. Optional: Set the monitor to connect to its manager automatically at start-up. From the Manager menu, choose Autoconnect.
7. When finished, end the session. From the Manager menu, choose Disconnect.

## Obtaining Queue Control


The Backburner monitor enforces a simple queue control mechanism to avoid conflicting requests from different users of the Backburner Windows Monitor. The first monitor establishing a connection to the manager is automatically granted queue control, and can perform all job-related activities, including stopping, restarting, or deleting jobs. Subsequently, other monitors connect in read-only mode, allow them to observe the activity on the Backburner network only. This section describes how to obtain queue control.

**NOTE:** When a Backburner Windows Monitor has queue control, advanced operations are not permitted in the Backburner *Web* Monitor, either. You will need to disconnect the Backburner Windows Monitor from its manager to permit these operations.

**To obtain queue control:**

1. From the Manager menu, choose Request Client List.

A Client List dialog appears, showing the status of all users connected to the manager via the Backburner Windows Monitor.




Client	User	Status	IP Address	Operating System
bristol	root	Read Only	172.16.128.143	Red Hat Enterprise Linux W/S release 3 (Taroon Up...
douala	marchac	Controller	172.16.128.224	Windows XP 5.1 Build 2600 - Service Pack 1
malta	hajn	Read Only	192.168.5.53	IRIX64 malta 6.5 01080747 IP27
mtipc73601	solesj	Read Only	172.16.56.33	Windows XP 5.1 Build 2600 - Service Pack 2
nicosi	root	Read Only	172.16.128.218	Red Hat Enterprise Linux W/S release 3 (Taroon Up...
sudan	duchesp	Read Only	192.168.5.104	IRIX64 sudan 6.5 01080747 IP30

OK

The Status column indicates the user with control of the queue.

2. Dismiss the dialog, then obtain queue control. From the Manager menu, choose Request Queue Control.

The manager transmits the request to the user currently with queue control. A message similar to the following appears on the remote machine.




3. As indicated in the dialog, the user has 10 seconds to actively refuse the request; otherwise, control of the queue passes over to you, and the status at the other workstation reverts to “read-only”.
4. You can now perform all operations on jobs and servers in on the Backburner network.
5. To release queue control, from the Manager menu, choose Disconnect.

This allows users of the Backburner *Web* Monitor to perform advanced operations.

## Backburner Web Monitor

The Backburner Web Monitor provides similar functionality to the Backburner Windows Monitor, and can be launched from any web browser with access to the Backburner network. For the user with administrator privileges, the functionality is identical to the Backburner Windows Monitor. For non-administrator users, most administration-level functionality is available, but only for jobs they themselves submit.



### Before You Begin

Before launching the Backburner Web Monitor, please note the following points:

- **USER ACCOUNT AND PASSWORD.** Depending on your system configuration, you may need a user name and password to access the Backburner Web Monitor. If your facility is using the Microsoft® IIS web server for Backburner, these will be your Windows username and password.
- **ADMINISTRATOR PRIVILEGES.** All users can perform common tasks on the jobs they themselves submit. For advanced tasks, and to control jobs submitted by others, an account with administrator privileges is required
- **QUEUE CONTROL.** Unlike the Backburner *Windows* Monitor, the Backburner *Web* Monitor does not enforce queue control. However, if a Backburner Windows Monitor is running and connected to the same manager, advanced operations—such as archiving and restoring jobs—are not permitted, and a “queue control” warning is returned. When this arises, release queue control by disconnecting the Backburner Windows Monitor from its manager.

## Required Privileges for Common Tasks

The following table indicates the privilege level required for tasks related to jobs.

Job Task	Normal User (Own Jobs)	Normal User (Other Jobs)	Admin User (All Jobs)
Activate	•	•	•
Suspend	•	•	•
Restart	•	•	•
Clone	•		•
Archive/Restore	•		•
Modify Settings	•		•
Delete	•		•

The following table lists the tasks related to render nodes (servers). All render node-related tasks require administrator privileges.

Server Task	Admin User
Shift jobs between servers/ server groups	•
Delete absent server	•
Set server availability schedule	•
Create server groups	•
Manage server group settings	•

## Launching the Backburner Web Monitor

### To launch the Backburner Web Monitor:


1. Open a web browser on a workstation that has access to the Backburner network.
2. In the browser's address field, enter `http://<machinename>/backburner`, where <machinename> is the name of the workstation running the Apache or IIS server. For example, if the name of the workstation is *caen*, the address is `http://caen/backburner`.

A pop-up dialog appears, prompting for a user name and password.




3. Enter a user name and password and then click OK. (The default user name and password is “backburner”).

The Backburner Web Monitor appears in the browser.





For accounts with administrator privileges, a complete set of controls is presented.




Otherwise, the set is more restricted, and some controls only appear next to jobs you yourself submitted.

- 4. When finished, end the session by closing the browser (or tab).

## WiretapCentral Backburner Monitor

WiretapCentral is a web application that provides interactive access to all media assets on your facility network. It presents editorial, visual effects and grading assets stored on any network-accessible Standard FS or Stone FS filesystem. The WiretapCentral Backburner Monitor integrated in it is an Adobe Flash Player compatible interface to the Backburner Manager, designed for tracking the progress of transcoding jobs initiated from WiretapCentral.



## Before You Begin

- **USER ACCOUNT AND PASSWORD.** Depending on your system configuration, you may need a user name and password to access WiretapCentral.
- **ADMINISTRATOR PRIVILEGES.** When user accounts have been implemented, you can perform tasks on the jobs you yourself submit. To control jobs submitted by others, an account with administrator privileges is required. Note that administrator privileges enable you to control all jobs on the Backburner network, not just the transcoding jobs submitted from WiretapCentral.
- **ARCHIVING:** Restoring archived jobs is not possible in the WiretapCentral Backburner Monitor. To restore an archived job, use the Backburner Windows Monitor instead.

## Launching the WiretapCentral Backburner Monitor

This section provides instructions on gaining access to the WiretapCentral Backburner Monitor and connecting to a Backburner Manager. For complete information on the UI, see the *WiretapCentral User Guide*.

### To gain access to the WiretapCentral Backburner Monitor:

1. Open a web browser on a workstation that has access to the Backburner network.
2. In the browser's address field, enter *http://<machinename>/WiretapCentral*, where <machinename> is the name of the workstation running WiretapCentral. For example, if the name of the workstation is *douala*, the address is *http://douala/WiretapCentral*.
3. From the Tools menu, select Backburner Monitor.  
The WiretapCentral Backburner Monitor appears in a new browser window or tab (depending on your browser settings).
4. From the Backburner Manager drop-down list, select the Backburner Manager of interest.  
The information in the current tab is updated automatically.
5. You can update the display manually by clicking the Refresh button, or you can set a refresh rate from the Auto Refresh menu.
6. To perform an operation on a job, select the job in the Jobs tab, then select the desired operation from the Action menu.  
**SHIFT-CLICK** or **CTRL-CLICK** to perform the same operation on more than one job at a time.
7. To view job details, double-click the job of interest.
8. When finished, end the session by closing the browser (or tab).

## Working with Jobs

Recapped briefly, a job flows from creative application to processing engine as follows. The creative application—Smoke, 3ds Max, Lustre, etc.—submits the job to the Backburner Manager, which distributes it as blocks of tasks to the Backburner Servers residing on the render nodes. The servers invoke the appropriate processing engine, which carries out its assigned tasks.

While it is the creative application that specifies the number of tasks in a particular job, once the job is on the Backburner network, it becomes the responsibility of the Backburner Manager. For example, it is the manager that decides how many tasks each render node is asked to carry out, in what order tasks are sent out, etc.

The process just described is largely automated and can operate entirely without user intervention. That being said, once a job is on the Backburner network, you can intervene in a number of ways, as described in this section.

### Monitoring

Basic monitoring allows you to view all the jobs submitted to Backburner, ensure jobs are being executed in the desired order, check the status of particular jobs, observe progress, view estimated times of completion, etc. It is the starting point for all other interactions.

For more information

- Windows Monitor: [“Finding and Monitoring Jobs”](#) on page 32
- Web Monitor: [“Finding and Monitoring Jobs”](#) on page 55

### Suspending and Reactivating

Suspending and reactivating jobs is commonly used to quickly improve job throughput and network efficiency. For example, you might suspend one job to temporarily assign its render nodes to another that is more urgent. Or, if you observe a particular job is taking too long, you can suspend it until off-peak hours, allowing shorter jobs to complete in the meantime. Sometimes, a low-priority job can ‘grab’ a processing node during the brief moment when it is between tasks—in such a case, suspending the low-priority job will return system resources to jobs with higher priorities.

**NOTE:** When a job is suspended, the render nodes assigned to it first complete the task they are processing, before taking on tasks from the next job in the queue.

For more information

- Windows Monitor: [“Suspending and Reactivating Jobs”](#) on page 34
- Web Monitor: [“Suspending and Reactivating Jobs”](#) on page 59

## Modifying Settings

Modify a job's settings to customize its properties, specify email notifications, change render node (server) assignments, or to set job dependencies.

- **PROPERTIES:** These include non-technical settings, such as the job description, plus a number of technical items that determine how the job is processed, including its priority and server group. For example, you could ensure quick processing by changing a job's priority and assigning it to a server group consisting of your fastest or most suitable render nodes.
- **NOTIFICATIONS:** These settings allow you to stay informed about a job's progress by email. For example, you can set Backburner to send email on job completion, or when every *n*th task is complete.
- **SERVERS:** Provides the ability to view the render nodes available for this type of job, those already assigned to it, and to add/remove nodes to/from the job. For example, suppose you submit a job to a server group. At any time, you can assign additional render nodes to the job, or take render nodes off the job, without modifying the server group definitions.
- **JOB DEPENDENCIES:** Set job dependencies to prevent a job from starting until one or more other jobs have completed.

**NOTE:** The job settings available for modification vary by processing engine. Some processing engines do not allow any job settings to be modified.

For more information

- Windows Monitor: [“Modifying Job Settings”](#) on page 35
- Web Monitor: [“Modifying Job Settings”](#) on page 60

## Restarting

While the most common workflow is to pause a job, change its settings, then re-activate the job, restarting a job is another possibility. Re-activating a paused job picks up processing from where it left off. That is, tasks already completed are not re-done. In contrast, restarting a job halts all processing for the job, clears the server of all job-related temporary files (including completed tasks), and restarts the job from its first task. It is identical to resubmitting the job from the creative application, without the need for that application to be running.

For more information

- Windows Monitor: [“Restarting Jobs”](#) on page 38
- Web Monitor: [“Restarting Jobs”](#) on page 63

## Cloning

Cloning a job creates a 100% duplicate job that is independent of the original, but inherits all its qualities, including its status and settings. Cloning is a convenient means for experimenting with changes to job settings or testing render nodes, since changes made to the clone do not affect the original. Note the following suggested uses and restrictions:

- **3DS MAX:** Cloning is an efficient means to compare the results generated by different processing engines, using exactly the same source models and materials.
- **LUSTRE:** Cloning is ideal for reprocessing a half-resolution Lustre job at full-resolution, once you receive approval from the colorist.
- **CLEANER XL:** Cloning can be used to test and compare the transcoding times of different workstations.
- **VISUAL EFFECTS AND FINISHING:** Cloning is allowed, but not generally recommended. For efficiency, the Visual Effects and Finishing applications pre-allocate space on the destination storage device for the frames resulting from all Burn and background I/O jobs. Since the clone is a duplicate of the original job, its results would overwrite those of the original job.

For more information

- Windows Monitor: [“Cloning Jobs”](#) on page 38
- Web Monitor: [“Cloning Jobs”](#) on page 63

## Archiving

Archiving conveniently removes completed jobs from the job queue. It is a practical means for keeping the job queue organized by reducing clutter. Its advantage over deleting completed jobs is in preserving all the information needed to re-submit the jobs at a later date. You can also restore an archived job simply to examine job details, such as the render nodes that processed it. This can assist in identifying problems—if unexpected or unsatisfactory results occurred, for example. Archiving can also be part of a facility backup strategy, since the archive represents a job history, in compact form. Note, however, that the job archive contains metadata (job details) only—it does not contain source material or rendered frames.

For more information:

- Windows Monitor: [“Archiving Jobs”](#) on page 39
- Web Monitor: [“Archiving Jobs”](#) on page 65

## Deleting

Deleting completely removes a job from the job queue and Backburner system. It does not, however, destroy source material or rendered results.

For more information

- Windows Monitor: [“Deleting Jobs”](#) on page 40
- Web Monitor: [“Deleting Jobs”](#) on page 67

## Working with Render Nodes

Render nodes are responsible for processing the tasks assigned to them by the Backburner Manager. The monitors provide several tools for managing the Backburner network at the level of the render nodes. These are aimed at making the Backburner network and job processing more efficient. For example, you can easily speed up processing of a large job by assigning new render nodes to it.

### Monitoring

Monitoring allows you to view, at a glance, the overall health of each render node on the Backburner network. Hardware details presented for each render node include the total RAM installed, and remaining disk space. Node status—*available*, *unavailable*, *idle*, *busy*, etc.—is also displayed, as well as details on any job the node is currently processing. Render nodes that have previously connected with the Backburner Manager but are no longer seen by it are easily identified, and can be removed, if desired.

For more information

- Windows Monitor: [“Monitoring Render Nodes”](#) on page 44
- Web Monitor: [“Monitoring Render Nodes”](#) on page 69

### Assigning

As noted, when a job is submitted by a creative application to Backburner for processing, the Backburner Manager automatically sends it as sub-jobs, called *tasks*, to render nodes for processing. Visual Effects and Finishing render tasks are sent to nodes on which Burn has been installed, 3ds Max tasks are sent to nodes equipped with 3ds Max, and so on. A task can consist of a single frame, a set of frames, or an entire clip, depending on the creative application and the nature of the work required.

The initial choice of render nodes for each job is determined automatically by Backburner, based on your Backburner settings. However, you can easily assign new nodes, or remove those currently assigned, as you see fit. For example, if a job has been sent to a particular server group, you can easily add nodes from outside the group to assist in the processing. When you add a node, Backburner sends the next task to the newly added node. When removing a node from a running job, keep in mind that a node always completes the task currently assigned to it. The only way to interrupt a node at work is by cancelling the entire job.

**NOTE:** Cleaner XL transcoding jobs and background Wire transfers are always assigned and processed by a single render node only. Adding additional nodes to these job types will not improve performance.

For more information

- Windows Monitor: [“Shifting Nodes Between Jobs”](#) on page 47
- Web Monitor: [“Shifting Nodes Between Jobs”](#) on page 72

## Deleting

When a Backburner Server connects to the Backburner Manager for the first time, the manager records the server’s presence on the Backburner network in its database. If the server subsequently fails to reconnect to the manager during a new session, or goes offline for any reason, the manager marks it as *absent*. Servers can go offline temporarily for any number of reasons: during a render node shutdown or reboot, network glitches, hardware updates, and so on. The next time the server comes online, it will simply re-connect to the manager and appear as available once again.

However, if you know a render node will be offline permanently, or for a considerable time, you can delete it from the network. For example, if you uninstall the Backburner Server, it will remain listed in the manager’s database. The old registration will cause a “ghost” node to appear in the list of servers, marked *absent*. The “ghost” can safely be deleted.

Deleting the node removes its entry from the database—it does not remove any software from the node itself. Some caution is nevertheless merited. Deleting a node can make it more difficult to troubleshoot jobs with problems, since it will be more difficult to determine which node carried out the flawed work. Before deleting a node, consider archiving jobs that made use of it, to preserve job details, including the nodes to which tasks were sent.

For more information

- Windows Monitor: [“Deleting Offline Render Nodes”](#) on page 48
- Web Monitor: [“Deleting Offline Render Nodes”](#) on page 74

## Scheduling

By default, nodes are always available for processing. However, you can easily limit render node availability, to manage network resources. For some creative applications, such as 3ds Max, creative seats themselves can be set up as render nodes. In such cases it can be helpful to limit rendering activity on those workstations to after hours. For others, such as the Visual Effects and Finishing applications, render nodes are always separate workstations. Nevertheless, scheduling can be useful. Burn nodes, for example, require access to the full resolution versions of the frames needing processing. This can result in a great deal of data

moving across the network. Scheduling some Burn nodes for only off-peak availability can assist in balancing network traffic levels until a more permanent solution is put in place.

For more information

- Windows Monitor: [“Setting Render Node Availability”](#) on page 48
- Web Monitor: [“Setting Render Node Availability”](#) on page 75

## Server Groups

A server group is a named collection of render nodes that is treated, for the most part, as if it were a single node. Recall that by default, jobs are submitted by creative applications to the Backburner network as a whole. It is the Backburner Manager that determines the specific render nodes to which they are sent, based on job type and node availability. However, certain Autodesk applications can be configured to submit jobs to a specific server group.

Server groups can be used to implement a job-processing strategy. For example, consider a facility with two Visual Effects and Finishing applications, and a render farm consisting of 8 Burn nodes, 4 of which are GPU-enabled. In such a situation, you might create two server groups, one each for the non-GPU and GPU-enabled Burn nodes. By assigning each Visual Effects and Finishing workstation to a different server group, you can reserve the GPU-enabled Burn nodes for the workstation with higher priority or more demanding jobs.

It should be understood that server groups do not restrict your ability to assign render nodes to particular jobs as you see fit. When a creative application is configured to submit its jobs to a server group, additional nodes can be assigned to it, automatically, or manually, once the job is on the network. Conversely, you can always remove individual nodes from a job, regardless of their relationship to a server group.

**NOTE:** To configure a Visual Effects and Finishing application to submit its jobs to a server group, set the optional *BackburnerManagerGroup* keyword in the application's *init.cfg* file. For more information see the *Burn Installation and User Guide*.

For more information

- Windows Monitor: [“Working with Server Groups”](#) on page 49
- Web Monitor: [“Working with Server Groups”](#) on page 76

## Server Group Customization

Customizing server group behaviour is made possible by way of two key options. First, you can configure a server group to automatically make use of non-group render nodes that are sitting idle. That is, when you have configured the creative application to submit jobs to a named server group, the Backburner Manager will send the job to any available non-group render nodes too. Second, by default the nodes in a server group are available to all jobs submitted to



the Backburner network. You can configure a server group to give priority to the jobs submitted to it specifically. Once configured, when the Backburner Manager receives a job for a server group, non-group jobs are immediately suspended, freeing up the nodes for the “server group” job.

For more information:

- Windows Monitor: [“Working with Server Groups”](#) on page 49
- Web Monitor: [“Working with Server Groups”](#) on page 76



# **Section 2**

## **Backburner Windows**

### **Monitor Reference**

Managing and Modifying Jobs – Windows	31
Managing Render Nodes – Windows	43



Image courtesy of Absolute Post

# Managing and Modifying Jobs – Windows

## Summary

<a href="#">Overview</a> .....	31
<a href="#">Finding and Monitoring Jobs</a> .....	32
<a href="#">Customizing the Job List</a> .....	33
<a href="#">Suspending and Reactivating Jobs</a> .....	34
<a href="#">Modifying Job Settings</a> .....	35
<a href="#">Restarting Jobs</a> .....	38
<a href="#">Cloning Jobs</a> .....	38
<a href="#">Archiving Jobs</a> .....	39
<a href="#">Deleting Jobs</a> .....	40

## Overview

The procedures in this chapter describe how to interact with jobs already submitted to Backburner for processing, using the Backburner Windows Monitor. For information on submitting jobs to Backburner from an Autodesk application, refer to the user guide for the application of interest.

**NOTE:** If the Backburner Windows Monitor title bar displays “Read Only,” this indicates another user has already connected to the manager via a Backburner Windows Monitor. To perform most of the tasks described in this chapter, you will need to obtain queue control. See [“Obtaining Queue Control”](#) on page 14.

## Finding and Monitoring Jobs

This section describes how to view all the jobs known to the Backburner Manager, their status and job details.

**To find jobs and view their status:**

1. Start the Backburner Monitor and connect to a Backburner Manager. See [“Backburner Windows Monitor”](#) on page 11.

The Job List area displays all the current jobs on the Backburner network. Their status, progress, and other information is also displayed.

[illegible]


a) Job list

The icon beside each job provides a visual indication of its state.

Icon Color	State
White	Not Started
Green	Active
Yellow	Suspended
Red	Error
Black	Completed

2. To find a job in the Job list:
  - Scroll through the entries using the scroll bars.
  - Reorder the list in ascending or descending order by clicking a column heading.

- Filter the list by first clicking the square on the right side of each column in the Job list. Enter filtering criteria in the dialog that appears.
3. Click on a job of interest to display its details in the Job Information area.



The Job Information area contains the following panels (information will vary depending on the job type).

Panel	Description
Job Summary	Lists important job-related information, including job options settings and output settings.
Task Summary	Lists tasks in the job (under "Task ID") along with each task's status, processing time, render node, and date and time of assignment. Right-click the task you wish to view under "Task ID" to view its output file. This is available only for completed tasks.
Job Details	Lists the job's rendering parameters, statistics, and settings.
Errors	Lists each frame for which an error occurred, which server registered the error, and a description of the error, such as missing maps, missing texture coordinates, or invalid output directories.

**HINT:** You can also create a new rendering job in the Backburner Monitor by pressing **ALT+N**, if the application-specific adapter supports this functionality.

## Customizing the Job List


You can add, remove and rearrange columns in the Job List to suit your preferences and needs.

**To customize the Job list:**

1. To add a new column:
- From the Jobs menu, choose Column Chooser.

• Right-click any job in the list and choose Column Chooser.

The Job Columns dialog appears, presenting the columns that can be added.



2. Drag and drop the column of interest to the column title bar in the Job list.
- Arrows appear when you are over a drop area.

Show All						
Job	Order	Priority			owner	
Burn_soldeu_06011...	1	50	Complete	{ 100% } 0...	flame9_7b1	
Burn_newcastle_06...	2	50	Complete	{ 100% } 0...	flame9_7b1	
Burn_newcastle_06...	3	50	Complete	{ 100% } 0...	flame9_7b1	
Burn_newcastle_06...	4	50	Complete	{ 100% } 0...	flame9_7b1	
Burn_newcastle_06...	5	50	Complete	{ 100% } 0...	flame9_7b1	

Dropping the column adds it to the UI and populates its rows with information for each job.

3. To rearrange the columns, drag and drop the column of interest to its new location.
4. To remove a column, right-click the column title, and choose Remove Column.


**NOTE:** You cannot remove the Job or Order columns.

## Suspending and Reactivating Jobs

Use the following procedures to suspend and reactivate jobs.




**To suspend a rendering job:**

1. Select one or more jobs in the Job list.
2. Do one of the following:
  - In the toolbar, click the Suspend button  (or press **CTRL+S**).
  - From the Jobs menu, choose Suspend.
  - Right-click a job in the Job list and choose Suspend.

The selected job is suspended. The icon for the job turns yellow to indicate the job's new status.

**NOTE:** If one of the selected jobs is completed, the Suspend button is disabled.

**To reactivate a suspended rendering job:**

1. Select a suspended job (indicated by a yellow icon).
2. Do one of the following:
  - In the toolbar, click the Activate button  (or press **CTRL+A**).
  - Right-click the job and choose Activate.
  - From the Jobs menu, choose Activate.

The selected job is reactivated and its icon changes from yellow to green. If another job is already being processed, the selected job becomes pending, and its icon turns white.

## Modifying Job Settings

Use the following procedure to modify job settings.

**To modify job settings:**

1. Select the job of interest in the Job list.
2. Display the current settings for the selected job:
  - From the Jobs menu choose Edit Settings.
  - Right-click the job and choose Edit Settings.
  - Press **CTRL+J**.

Settings for the job appear in a dialog similar to the following.

Job Settings	
Job Name	The Constant Writer
Job Description	Calling: ping
Restart Job	No
Override Global Blocking Tasks	No
Enable Blocking Tasks	No
Use All Available Servers	Yes
Server Limit	0
Server Group	
Command Line Tool Settings	
cmd arguments	ping localhost
Working path	
Log path	
Task timeout (minutes)	600
Output files	
Notifications	
Enable Notifications	No
Notify Failures	No
Notify Progress	Yes
Notify Completion	No
Notify Progress Every Nth Task	5
Send Emails	Yes

**NOTE:** Job settings vary, depending on the job type and processing engine.

3. Double-click the field of interest, and modify it as desired.

If the job setting can be modified, you are allowed to change it. Otherwise, the setting remains unchanged.

4. Modify the Job properties as desired:

Item	Description
Description	The description provided when the job was submitted to Backburner.
Priority	The job priority, from 0 to 100. Zero is the highest priority. 100 means the job is suspended.
Override Task Blocks Setting	Depending on how your system administrator has configured the Backburner Manager, it either i) assigns multiple tasks to each render node—that is, <i>blocks</i> of tasks (the default setting), or ii) assigns each render node one task at a time. Enable to override the manager’s configuration, for this particular job.

Item	Description
Enable Task Blocks	Enable to cause the manager to send render nodes blocks of tasks, for this job. Disable if you want each render node to receive only one task at a time, for this job. For example, enabling for frame-based render jobs results in each render node receiving a block of several frames to render at once. Disabling results in frames being sent one at a time. For this setting to have an effect, you must also enable <i>Override Task Blocks Setting</i> .
Use All Available Servers	Overrides any Backburner Manager settings that restrict the maximum number of servers that can work on this job at any one time.
Server Limit	The maximum number of servers that can work on this job at any one time. Set this to zero to run on all servers.
Server Group	The server group to which the job is assigned. Only servers in the specified server group will work on the given job, unless the group is set to use idle non-group servers.

5. The Backburner Manager can send job success, failure and other notifications to the email addresses you specify in the Notifications area.

Item	Description
Enable Notifications	Turns on/off notifications for the job.
Notify Failures	Enable to be notified on job failure.
Notify Progress	Enable for notification by email as each render node completes its block of tasks.
Notify Completion	Enable for email notification on job completion.
Notify Progress Every Nth Task	Enable for email notification when each <i>n</i> th task is completed.
Send Emails	Enable email notification. To receive email notifications, both this setting and the Enable Notifications must be enabled.
Alert Email From	Return address used by the Backburner Manager when sending notification email.
Alert Email To	Destination address.
Alert Email Server	Server where the smtp mailer daemon is running.

6. Click OK to apply the modified settings to the job.

If the job is currently being processed, the new settings only apply to the work remaining; tasks in progress and completed tasks are unaffected.

**HINT:** To apply your changes to all a job's tasks, reprocess the job from the beginning. See [“Restarting Jobs”](#) on page 38.

## Restarting Jobs

Use the following procedure to restart jobs.

### To restart a job:

1. Select the job(s) of interest.
2. Do one of the following to restart the selected job(s):
  - From the Jobs menu, choose Restart Job.
  - Right-click the job and then choose Restart Job.
3. When prompted, click OK to restart the job(s).

The selected jobs are restarted and their icons change to green. If another job is already being processed, the restarted jobs becomes pending, and their icons turn white.

## Cloning Jobs

Use the following procedure to clone a job.

### To clone a job:

1. Select the job of interest.
2. Do one of the following:
  - From the Jobs menu choose Clone Job.
  - Right-click the job and then choose Clone Job.

The job is duplicated and its clone appears in the Job list with the same name and job status. The description field indicates the job is a clone.
3. Modify job settings for the clone, as desired. See [“Modifying Job Settings”](#) on page 35.

The job settings for a clone are identical to those of its parent job. You can modify these settings to customize how the clone is to be processed by the system.

4. Depending on the status of the clone, you may wish to take further action, as indicated in the following table.

Status	Suggested Action
Pending	Allow the job to be processed following the normal sequence of events. No action necessary.
Suspended	Restart or reactivate the job. See <a href="#">“Suspending and Reactivating Jobs”</a> on page 34.
Completed	Restart the job. See <a href="#">“Restarting Jobs”</a> on page 38.

## Archiving Jobs

Use the following procedures to archive a job, restore an archived job, or delete a job from the archive. Jobs can be archived automatically, when the manager has been configured to do so. You can also archive jobs directly from the monitor, as explained here. Note that archiving a job has no effect upon the associated media. The job archive contains job metadata only; that is, it contains the information needed to restart a job, but not the source media.

### To archive a job:


1. Select the job of interest.
2. Do one of the following to archive the selected job:
  - From the Jobs menu choose Archive Job.
  - Right-click the job and then choose Archive Job.
3. When prompted, click OK.
 

The job is archived and removed from the Job list. By default, archived jobs are saved to the *Network\Archive* folder where the Backburner Manager is installed.

### To restore or delete a job from the archive:

1. Display the Job Archive dialog:
  - From the Jobs menu, choose Job Archives.
  - Right-click any job in the Job list and choose Job Archives.

The Job Archive dialog appears, presenting information for all archived jobs. The columns and information presented are fixed.



**HINT:** Click Refresh if you do not see all the jobs expected.

2. Select a job (or jobs) and perform the desired action, as explained in the following table.

Action	Result
Delete	Removes the job from the archive. Since deletion cannot be undone, you are asked to confirm your action.
Activate	Restores a selected job to the job queue, removing it from the archive. You can then choose to modify its settings and restart the job. Jobs reappear in the job queue with the settings they had when archived. This includes job status. If a job was suspended or completed when it was archived, once restored you must re-activate or restart it to start the processing again.
Refresh	Updates the display with the most recently archived jobs.


3. Once finished, close the Job Archives dialog to return to the Backburner Windows Monitor.

## Deleting Jobs

Use the following procedure to delete jobs from the job queue.

**NOTE:** Deleting cannot be undone. If you think you may need to run the job again in the future, or examine job details, consider archiving it instead. See [“Archiving Jobs”](#) on page 39.

**To delete a job:**

1. Select the job(s) of interest.
2. Do one of the following:
  - In the toolbar, click the Delete button  (or press **DELETE**).
  - From the Jobs menu, choose Delete.
  - Right-click a job in the Job list and choose Delete.
3. When prompted to confirm your action, click OK.  
The selected jobs are deleted.





# Managing Render Nodes – Windows

## Summary

<a href="#">Overview</a> .....	43
<a href="#">Monitoring Render Nodes</a> .....	44
<a href="#">Customizing the Render Node List</a> .....	46
<a href="#">Shifting Nodes Between Jobs</a> .....	47
<a href="#">Deleting Offline Render Nodes</a> .....	48
<a href="#">Setting Render Node Availability</a> .....	48
<a href="#">Working with Server Groups</a> .....	49

## Overview

The procedures in this chapter relate to managing the render farm at the level of its render nodes, using the Backburner Windows Monitor.

**NOTE:** If the Backburner Windows Monitor title bar displays “Read Only”; this indicates another user has already connected to the manager via a Backburner Windows Monitor. To perform most of the tasks described in this chapter, you will need to obtain queue control. See [“Obtaining Queue Control”](#) on page 14.


## Monitoring Render Nodes

Use the following procedure to monitor the status of render nodes.

### To view render node status:

1. Start the Backburner Monitor and connect to a Backburner Manager. See [“Backburner Windows Monitor”](#) on page 11.

The Server List area occupies the lower panes in the monitor. This area shows nodes organized in a hierarchical tree view and as a list.



a) Tree View

b) List View

The tree view presents a hierarchical list of all node groups, as well as the plug-ins available for the system. You can use this area to see which render nodes are available to render jobs, as well as manage groups of nodes.

The list of render nodes shows all nodes assigned to the group selected in the tree view. If no group is selected, all render nodes on the system appear in this area. By default, this area shows the following information for each node:


- The name and current status of the node.
- The job the node is currently processing.
- The most recent message sent by the node to the Backburner Manager.

The icon beside each server provides a visual indication of its state.

Icon Color	State
Green	OK
Yellow	Idle
Grey	Absent
Red	Error

2. Customize the information shown in the list of render nodes, as desired. See [“Customizing the Render Node List”](#) on page 46.
3. To locate a render node, do any of the following:
  - Scroll through the entries using the scroll bars.
  - Reorder the list in ascending or descending order by clicking a column heading.
  - Filter the list by first clicking the square on the right side of each column in the Job list. Enter filtering criteria in the dialog that appears.
4. Right-click a render node and choose Properties (or press **CTRL+N**).

The Server Properties dialog appears, showing hardware and software information for the node.



Item	Description
<b>General</b>	
Server	Server host name.
User	User account name under which the Backburner Server was launched.
Current Job	The current job as assigned by the Backburner Manager.
Status	Current server activity.
Handle	Server ID, used internally and in log files.
Platform	Operating system details.
Memory	Installed RAM.
CPUs	The total number of CPUs installed on the system.
IP address	The server's IP address. This is used by the Backburner Manager to communicate with the server.
Perf. Index	A value in the range [0–1] indicating the performance level of the render node, relative to the other servers on the same job. A score of 1 indicates this is the best-performing server.
Available Disk Space	Disk space available for rendering.

Item	Description
<b>Plugin Summary</b>	
burn, mio, Command Line Tool, Wire, etc.	A list of adapters installed on the render node, for example: <ul style="list-style-type: none"> <li>• burn: The Burn renderer.</li> <li>• mio: The Media I/O adapter used by WiretapCentral.</li> <li>• Command Line Tool: The adapter associated with cmdjob.</li> </ul>
<b>Module Info</b>	
Server	Backburner Server software version.
Backburner API	DSO version. Should match the Backburner software version.
Plugin	Backburner Adapter version and platform info.


## Customizing the Render Node List

Similarly to the Job list, you can add, remove, and rearrange columns in the render node list to suit your preferences and needs.

### To customize the render node list:

1. To add a new column:
  - From the Server menu choose Column Chooser.
  - Right-click any node in the list and choose Column Chooser.

The Server Columns dialog appears, presenting the columns that can be added.



2. Drag and drop the column of interest to the column title bar in the Job list.

Arrows appear when you are over a drop area.

Show All				
All Servers				
Server	Status	Current Job	Last M	
burn10	Absent	None	N/A	
burn3	Absent	None	N/A	
burn4	Absent	None	N/A	
burn5	Idle	None	None	
burn8	Idle	None	None	
burn9	Absent	None	N/A	
cleanerlab2	Idle	None	None	
douala	Idle	None	None	
newcastle	Idle	None	None	
soldeu	Idle	None	None	
wick	Idle	None	None	

Dropping the column adds it to the UI and populates its rows with information for each node.


3. To rearrange the columns, drag and drop the column of interest to its new location.
4. To remove a column, right-click the column title, and choose Remove Column.

**NOTE:** You cannot remove the Server column.

## Shifting Nodes Between Jobs

Use the following procedure to shift a render node from one job to another.

### To shift a render node:

1. Select the node in the server list, then click the Remove Server icon  on the toolbar.  
The node ends its current processing task and becomes available for other jobs.
2. In the job list, select the job to which you want to assign the node.
3. Assign the render node to the job:
  - Select the unassigned node and then, from the Servers menu, choose Assign To Selected Jobs.
  - Right-click the unassigned node and choose Assign To Selected Jobs from the popup menu.

The selected render node begins working on the new job. It remains assigned to the new job until the entire job is complete.

## Deleting Offline Render Nodes

Use the following procedure to delete offline render nodes from the system. Deleting a render node removes its entry from the database maintained by the Backburner Manager. It does not delete any software from the node itself.

### To delete a render node:

1. Select the render node(s) of interest.  
Only nodes marked by the system as *absent* can be deleted.
2. Do one of the following:
  - From the Servers menu, choose Delete Server.
  - Right-click node and choose Delete Server.
 The node is deleted and are removed from the list.


## Setting Render Node Availability

Use the following procedure to schedule the availability of a render node.

### To schedule the availability of a render node:

1. Select the render node(s) of interest.
2. Do one of the following:
  - Right-click the node and choose Week Schedule.
  - From the Servers menu, choose Week Schedule.

The schedule for the render node appears.



Periods of time that are green indicate the node is available to process jobs. By default, nodes are always available.

3. Select the time of interest:


- Select a single hour by clicking the hour of interest.
- Select the same hour for each day with one click using the hour buttons.
- Click and drag to select a number of hours at once.
- Select a whole day using the days-of-the-week buttons.
- Select the entire week by clicking the button at the top left.

The selected time is shown in white.

4. Click the Allow or Disallow buttons, as desired.

Green indicates node availability. Red indicates processing is prohibited during this time.

The following schedule shows a render node that is available weekdays at night and 24 hours a day on weekends. This might be the case for a creative workstation used as a render node after-hours, for example.



5. Click OK to update the schedule for the node and close the dialog.

## Working with Server Groups

Use the following procedures to create or delete a named collection of render nodes, called a *server group*, and to assign a server group to a job.


**NOTE:** Two kinds of server groups can be created, *local* groups and *global* groups. In almost all cases, you will want to create global server groups only. Local groups serve a particular purpose for 3ds Max, under a specific Backburner configuration. The configuration in question has all three of 3ds Max, the Backburner Manager and Backburner Monitor installed and running on the local machine. In this case, a local group is a shortcut to a list of render nodes individually selectable from within the 3ds Max application. In all other cases—and for all other Autodesk applications—create global groups, as described in this section.

**NOTE:** For information on configuring a creative application to submit jobs to a server group, see the User Guide for application of choice. To configure a Visual Effects and Finishing application to submit its jobs to a server group, set the optional *BackburnerManagerGroup* keyword in the application's *init.cfg* file. For more information see the *Burn Installation and User Guide*.

**To create a server group:**

1. Right-click All Servers in the server list and choose Global Group from the popup menu. If the option is greyed-out, connect to a Backburner Manager then try again.

The Server Group dialog appears.



2. Configure the behaviour of the group as desired.

Item	Description
Name	The name of the server group as it will appear in the UI.
Weight	Adjusts the priority of jobs assigned to the server group. Jobs assigned to a high-weight server group are given higher priorities than jobs assigned to lower-weight groups. In fact, a job assigned to a high-weight group may be rendered ahead of non-group jobs—even if the non-group jobs have higher priorities at the job-level.



Item	Description
Can Use Idle Non-group Servers	Enable to allow the Backburner Manager to temporarily assign idle non-group render nodes to the group. Enabling this option increases the rendering power of the group.
Suspend Non-Current Group Jobs	Enable to allow the Backburner Manager to suspend the processing of non-group jobs running on group nodes, when a new job is submitted specifically to the group. Enabling this option allows a render node group to automatically switch from non-group jobs to new group-jobs.

3. Add render nodes to the group by selecting them in the *Available* list and clicking Add.

The render nodes are added to the group.

**HINT:** You can add render nodes directly from the Server list area by dragging and dropping them onto an already existing group.

4. Once you are satisfied with your choices, click OK to commit the changes.

The render node group is added to the Global Groups list.

#### **To assign a server group to a job:**

1. Select the job(s) of interest in the Job list.
2. In the Server list, right-click the server group and choose Assign Group to Selected Jobs.

The server group is assigned to job.

- If nodes in the group are busy, they complete their currently-assigned jobs before working on the new job to which you have assigned them. Otherwise, they begin working on the new job immediately.
- If the “Suspend current non-group jobs” option is enabled for the group, all nodes in the Server group drop their current rendering job and begin processing the assigned job immediately.

#### **To shift a server group between two jobs:**

1. Select all jobs in the Job list.
2. In the Global Groups list, right-click the render node group to be reassigned and choose Remove Group From Selected Jobs.

Each render node in the group ends its current assignment and becomes available for other jobs. If *Suspend current non-group jobs* option is enabled for the group, the jobs are dropped immediately.

**NOTE:** Server groups are subject to the same job assignment and completion rules and restrictions as individual render nodes. See [“Shifting Nodes Between Jobs”](#) on page 47.

3. In the Job list, select the job to which you want to assign the group.
4. In the Server list, right-click the server group and choose Assign Group to Selected Jobs. The render node group is assigned to the new job and begins rendering.

If *Can use idle non-group servers is enabled* for the group, the Backburner Manager adds nodes to the group temporarily, as they become available from other jobs.

**To delete a Server group:**

1. In the Global Groups list, right-click the render node group of interest and choose Delete Group.
2. When prompted to confirm your action, click Yes.  
The group is deleted from the Server list. The render nodes themselves remain untouched, and can be assigned to other groups, as needed.

# **Section 3**

# **Backburner Web Monitor**

# **Reference**

Managing and Modifying Jobs – Web

55

Managing Render Nodes – Web

69



Image courtesy of Finish

# 5

## Managing and Modifying Jobs – Web

### Summary

<a href="#">Overview</a> .....	55
<a href="#">Finding and Monitoring Jobs</a> .....	55
<a href="#">Suspending and Reactivating Jobs</a> .....	59
<a href="#">Modifying Job Settings</a> .....	60
<a href="#">Restarting Jobs</a> .....	63
<a href="#">Cloning Jobs</a> .....	63
<a href="#">Archiving Jobs</a> .....	65
<a href="#">Deleting Jobs</a> .....	67

### Overview

The procedures in this chapter describe how to interact with jobs already submitted to Backburner for processing, using the Backburner Web Monitor. For information on submitting jobs to Backburner from an Autodesk application, refer to the user guide for the application of interest.

**NOTE:** If the Backburner Web Monitor returns an error message indicating “queue control is needed for the requested operation”, it indicates a Backburner *Windows* Monitor is already connected to the Backburner Manager. To obtain queue control, disconnect the Backburner Windows Monitor from the manager. For a more complete discussion, see [“Obtaining Queue Control”](#) on page 14.


### Finding and Monitoring Jobs

This section describes view all the jobs known to the Backburner Manager, their status and job details.

**To find jobs and view their status:**

1. Launch a web browser and log in to the Backburner Web Monitor. See [“Backburner Web Monitor”](#) on page 16.
2. Click the Jobs tab.

The Job list appears, showing all jobs on the system. Their status, progress, and other information is also displayed.




Job Name	Status	Progress	Tasks	Priority	Submitted	Started	Plugin	Owner	Controls
Burn_soldier_060613_17.33.21(+)	Waiting	4 %	3 / 70	50	06/13/2006 at 05:44:24 PM	06/14/2006 at 10:02:02 AM	burn 2007	flame2007	Suspend Restart
Burn_soldier_060613_17.33.11	Not Started	0 %	0 / 70	50	06/13/2006 at 05:44:15 PM	Unknown	burn 2007	flame2007	Suspend Restart
Burn_soldier_060613_17.35.30	Suspended	0 %	0 / 70	50	06/13/2006 at 05:15:40 PM	Unknown	burn 2007	flame2007	Activate Restart
Burn_soldier_060613_17.13.43	Not Started	0 %	0 / 70	50	06/13/2006 at 05:13:43 PM	Unknown	burn 2007	flame2007	Suspend Restart
Burn_soldier_060613_16.53.46	Waiting	9 %	6 / 70	50	06/13/2006 at 04:53:47 PM	06/14/2006 at 10:02:14 AM	burn 2007	flame2007	Suspend Restart
Burn_soldier_060613_16.25.09	Suspended	0 %	0 / 70	50	06/13/2006 at 04:25:10 PM	Unknown	burn 2007	flame2007	Activate Restart
Burn_soldier_060613_16.09.00	Suspended	0 %	0 / 70	50	06/13/2006 at 04:09:01 PM	Unknown	burn 2007	flame2007	Activate Restart
Burn_soldier_060613_16.04.31	Complete	100 %	70 / 70	50	06/13/2006 at 04:04:31 PM	06/13/2006 at 04:04:32 PM	burn 2007	flame2007	Restart
Burn_soldier_060614_09.37.30	Active	20 %	20 / 100	50	06/14/2006 at 09:37:30 AM	06/14/2006 at 10:02:54 AM	burn 2007	flame2007	Suspend Restart
Burn_soldier_060614_09.37.17	Complete	100 %	100 / 100	50	06/14/2006 at 09:37:16 AM	06/14/2006 at 09:37:16 AM	burn 2007	flame2007	Restart
Burn_soldier_060614_09.11.12	Active	52 %	52 / 100	50	06/14/2006 at 09:11:13 AM	06/14/2006 at 10:02:29 AM	burn 2007	flame2007	Suspend Restart

**NOTE:** If there are more than 20 jobs, page numbers appear at the bottom of the monitor.

The icon beside each job provides a visual indication of its state.

Icon Color	State
White	Not Started
Green	Active
Yellow	Suspended
Red	Error
Black	Completed

3. To filter the list, type the word you want to match in the Search For field, select a column from the By Column drop, and click the Refresh button (or press **ENTER** on the keyboard).



The job list is reduced to those matching your filtering criteria.

**NOTE:** Filtering is performed on all jobs in the system, not just those on the first page of the display.

- Click on a job of interest to view its details.

The screenshot shows the Autodesk Backburner application window. The title bar reads 'BACKBURNER Autodesk'. The interface includes a menu bar with 'Jobs', 'Servers', 'Server Groups', 'Archives', and 'About'. Below the menu bar is a search bar with 'Search For:' and 'By Column: Select Column'. A 'Refresh' button is located to the right of the search bar. The main content area displays job details for 'Burn\_soldeu\_000013\_17.13.14'. The job is owned by 'flame2007b5', submitted from 'soldeu', and submitted on '06/13/2006 at 05:44:15 PM'. The job status is 'Complete' with 100% progress, 7 servers, and a priority of 50. A table below shows the job's progress, with columns for 'State', 'Progress (%)', 'Servers', 'Priority', 'Tasks', 'Average Task Time', 'Estimated Time Left', and 'Plugin'. The job properties section shows the handle '1460087880', description 'MOTION\_spark', job type 'burn 2007.0', start time '06/14/2006 at 10:08:51 AM', end time '06/14/2006 at 10:08:32 AM', last updated time '06/14/2006 at 10:08:54 AM', and 0 dependencies. A summary table at the bottom lists 15 tasks, all of which are 'Complete' with a time elapsed of '00:00:02' and were executed on 'burn8'.

Task ID	Status	Time elapsed	Server	Last errors
1	Complete	00:00:24	burn0	
2	Complete	00:00:22	burn4	
3	Complete	00:00:16	burn5	
4	Complete	00:00:03	burn0	
5	Complete	00:00:02	burn0	
6	Complete	00:00:02	burn0	
7	Complete	00:00:01	burn0	
8	Complete	00:00:01	burn0	
9	Complete	00:00:02	burn0	
10	Complete	00:00:03	burn0	
11	Complete	00:00:02	burn0	
12	Complete	00:00:02	burn0	
13	Complete	00:00:02	burn0	
14	Complete	00:00:02	burn0	
15	Complete	00:00:02	burn0	

Item	Description
<b>General Area</b>	
Name	The job display name.
Owner	Name of the user that submitted the job.
Submitted From	Name of the host from which the job was submitted.
Submitted	The time at which the job was originally submitted.
State	Current state of the job: <ul style="list-style-type: none"> <li>• complete: Completed successfully.</li> <li>• active: Currently being serviced</li> <li>• suspended: On hold.</li> <li>• idle: Not scheduled for service.</li> <li>• waiting: Ready, and waiting to be serviced.</li> </ul>
Progress (%)	Number of tasks completed, expressed as a percentage.
Servers	The number of servers to which the job has been submitted.
Priority	The job priority, from 0 to 100. Zero is the highest priority. 100 means the job is suspended.
Tasks	The number of tasks completed and total number of tasks.

Item	Description
Average Task Time	The average time to complete each task, so far.
Estimated Time Left	Time remaining until job completion.
Plugin	Name of the adapter required for the job, for example: <ul style="list-style-type: none"> <li>• Burn: The Burn renderer.</li> <li>• mio: The Media I/O adapter used by WiretapCentral.</li> <li>• Command Line Tool: The adapter associated with cmdjob.</li> </ul>
<b>Job Properties</b>	
Handle	The job's ID as assigned by the Backburner Manager.
Description	The description provided when the job was submitted to Backburner.
Job Type	Name of the adapter required for the the job.
Started	The time at which the job was started, in the following format: YYYY/MM/DD HH:MM:SS. If the job has not yet started, zeros appear for the values.
Ended	The time at which the job completed. If the job is not finished, the time appears as a series of zeros: 0000/00/00 00:00:00.
Last Updated	The last time the browser was refreshed.
# of Dependencies	Any jobs on which the current job is dependent. A job will be started only the jobs on which it is dependent are complete.
<b>Summary</b>	
Task ID	The task number. Jobs are normally sent for rendering as blocks of tasks.
Status	The state of the task (active, complete, waiting, error).
Time elapsed	The time duration consumed by the task (HH:MM:SS:MS).
Server	The name of the server where the task is being executed.
Last errors	The last execution error message, if any.

5. Click the Jobs tab to return to the list of all jobs.



Dependencies are also indicated by an asterisk following the job name.

Job Name	Status	Progress	Tasks	Priority	Submitted	Started	Plugin	Owner	Controls
Burn_soldieu_060613_17.44.21.13	Waiting	4 %	3 / 70	50	06/13/2006 at 05:44:24 PM	06/14/2006 at 10:02:02 AM	burn 2007	flame2007	Suspend Restart
Burn_soldieu_060613_17.45.13	Not Started	0 %	0 / 70	50	06/13/2006 at 05:44:15 PM	Unknown	burn 2007	flame2007	Suspend Restart
Burn_soldieu_060613_17.46.30	Suspended	0 %	0 / 70	50	06/13/2006 at 05:45:40 PM	Unknown	burn 2007	flame2007	Activate Restart
Burn_soldieu_060613_17.43.43	Not Started	0 %	0 / 70	50	06/13/2006 at 05:13:43 PM	Unknown	burn 2007	flame2007	Suspend Restart
Burn_soldieu_060613_16.53.46	Waiting	9 %	6 / 70	50	06/13/2006 at 04:53:47 PM	06/14/2006 at 10:02:14 AM	burn 2007	flame2007	Suspend Restart
Burn_soldieu_060613_16.25.09	Suspended	0 %	0 / 70	50	06/13/2006 at 04:25:10 PM	Unknown	burn 2007	flame2007	Activate Restart
Burn_soldieu_060613_16.09.00	Suspended	0 %	0 / 70	50	06/13/2006 at 04:09:01 PM	Unknown	burn 2007	flame2007	Activate Restart
Burn_soldieu_060613_16.04.31	Complete	100 %	70 / 70	50	06/13/2006 at 04:04:31 PM	06/13/2006 at 04:04:32 PM	burn 2007	flame2007	Restart
Burn_soldieu_060614_09.37.30	Active	20 %	20 / 100	50	06/14/2006 at 09:37:36 AM	06/14/2006 at 10:02:54 AM	burn 2007	flame2007	Suspend Restart
Burn_soldieu_060614_09.37.17	Complete	100 %	100 / 100	50	06/14/2006 at 09:37:18 AM	06/14/2006 at 09:37:18 AM	burn 2007	flame2007	Restart
Burn_soldieu_060614_09.11.12	Active	52 %	52 / 100	50	06/14/2006 at 09:11:13 AM	06/14/2006 at 10:02:29 AM	burn 2007	flame2007	Suspend Restart

## Suspending and Reactivating Jobs

Use the following procedures to suspend and reactivate jobs.

### To suspend a rendering job:

1. Click the Jobs tab and locate the job you want to suspend.
2. Click the Suspend button next to the job of interest.

**NOTE:** If the selected job is completed, the Suspend button is not present in the interface.

3. Confirm the action in the pop-up dialog that appears.

The selected job is suspended. The icon for the job turns yellow to indicate the job's new status.

### To reactivate a suspended rendering job:

1. Click the Jobs tab and locate a suspended job (indicated by a yellow icon).
2. Click the Activate button next to the job of interest.
3. Confirm the action in the pop-up dialog that appears.


The selected job is reactivated and its icon changes from yellow to green. If another job is already being processed, the selected job becomes pending, and its icon turns white.

## Modifying Job Settings

Use the following procedure to modify job settings.

### To modify job settings:

1. On the Jobs tab, click the Settings button next to the job of interest.



The screenshot shows the BACKBURNER web interface with the 'Jobs' tab selected. A table lists various jobs with columns for Job Name, Status, Progress, Tasks, Priority, Submitted, Started, Plugins, Owner, and Controls. The 'Settings' button in the Controls column for the first job is highlighted.

Job Name	Status	Progress	Tasks	Priority	Submitted	Started	Plugins	Owner	Controls
burn_sol00u_000013_12.44.23.0	Not Started	0 %	0 / 70	50	06/13/2008 at 05:44:24 PM	Unknown	burn 2007	fame2007	Suspend Restart Clone Archive Settings Delete
burn_sol00u_000013_12.44.11	Not Started	100 %	70 / 70	50	06/13/2008 at 05:44:15 PM	06/14/2008 at 10:06:51 AM	burn 2007	fame2007	Suspend Restart Clone Archive Settings Delete
burn_sol00u_000013_12.45.39	Suspended	0 %	0 / 70	50	06/13/2008 at 05:16:40 PM	Unknown	burn 2007	fame2007	Activate Restart Clone Archive Settings Delete
burn_sol00u_000013_12.13.43	Active	71 %	50 / 70	40	06/13/2008 at 05:13:43 PM	06/14/2008 at 10:08:58 AM	burn 2007	fame2007	Suspend Restart Clone Archive Settings Delete
burn_sol00u_000013_16.53.48	Complete	100 %	79 / 70	50	06/13/2008 at 04:53:47 PM	06/14/2008 at 10:03:14 AM	burn 2007	fame2007	Restart Clone Archive Settings Delete
burn_sol00u_000012_16.25.09	Suspended	0 %	0 / 70	50	06/13/2008 at 04:25:10 PM	Unknown	burn 2007	fame2007	Activate Restart Clone Archive Settings Delete
burn_sol00u_000012_16.09.09	Suspended	0 %	0 / 70	50	06/13/2008 at 04:09:01 PM	Unknown	burn 2007	fame2007	Activate Restart Clone Archive Settings Delete
burn_sol00u_000012_16.04.31	Active	0 %	0 / 70	50	06/13/2008 at 04:04:31 PM	06/14/2008 at 10:14:35 AM	burn 2007	fame2007	Suspend Restart Clone Archive Settings Delete
burn_sol00u_000011_09.37.39	Complete	100 %	100 / 100	50	06/14/2008 at 09:37:39 AM	06/14/2008 at 10:08:12 AM	burn 2007	fame2007	Restart Clone Archive Settings Delete
burn_sol00u_000011_09.37.17	Complete	100 %	100 / 100	50	06/14/2008 at 09:37:18 AM	06/14/2008 at 09:37:18 AM	burn 2007	fame2007	Restart Clone Archive Settings Delete
burn_sol00u_000011_09.13.12	Complete	100 %	100 / 100	50	06/14/2008 at 09:11:13 AM	06/14/2008 at 10:02:29 AM	burn 2007	fame2007	Restart Clone Archive Settings Delete

Settings for the job appear in the monitor.

**BACKBURNER** Autodesk

Jobs Servers Server Groups Archives About

Search For: By Column: Select Column Refresh

burn\_sovex\_000013\_17.45.32 Apply Apply & Restart Cancel

**Job Properties**

Description: MOTION\_epark

Priority: 50 (0=Highest, 100=Lowest)

Override Global Blocking Tasks: ☐

Enable Blocking Tasks: ☐

Use All Available Servers: ☒

Server Limit: 0

Server Group:

**Notifications**

Enable Notifications: ☐

Notify Failures: ☐

Notify Progress: ☐

Notify Completion: ☐

Notify Progress Every Job Task: ☐

Send Emails: ☐

Alert Email From:

Alert Email To:

Alert Email Server:

**Servers**

Available Servers Assigned Servers

burn1  
valeria  
spide  
burn2  
burn3  
burn4  
cam  
lara

burn14  
burn11  
burn13  
burn12

Add Remove

**Job Dependencies**

Available Dependencies Current Dependencies

burn\_sovex\_000014\_09.11.12  
burn\_sovex\_000013\_16.03.41  
burn\_sovex\_000013\_16.08.00  
burn\_sovex\_000014\_09.37.38  
burn\_sovex\_000014\_09.37.17  
burn\_sovex\_000013\_16.04.21  
burn\_sovex\_000013\_17.44.21

Add Remove

The Job Settings page is divided into the following main areas:

Area	Description
Job Properties	Settings relating to how the job is processed.
Notifications	Allows you to receive email notification of job progress.
Servers	Assign and remove render nodes to and from the job.
Job Dependencies	Set job dependencies to prevent this job from starting until one or more others have completed.

## 2. Modify the Job Properties as desired:

Item	Description
Description	The description provided when the job was submitted to Backburner.
Priority	The job priority, from 0 to 100. Zero is the highest priority. 100 means the job is suspended.
Override Task Blocks Setting	Depending on how your system administrator has configured the Backburner Manager, it either i) assigns multiple tasks to each render node—that is, <i>blocks</i> of tasks (the default setting), or ii) assigns each render node one task at a time. Enable this checkbox to override the manager's configuration, for this particular job.
Enable Task Blocks	Enable this checkbox to cause the manager to send render nodes blocks of tasks, for this job. Leave it unchecked if you want each render node to receive only one task at a time, for this job. For example, enabling this check box for frame-based render jobs, results in each render node receiving a block of several frames to render at once. Leaving it unchecked results in frames being sent one at a time. For this checkbox to have an effect, you must also enable <i>Override Task Blocks Setting</i> .
Use All Available Servers	Overrides any Backburner Manager settings that restrict the maximum number of servers that can work on this job at any one time.
Server Limit	The maximum number of servers that can work on this job at any one time. Set this to zero to run on all servers.
Server Group	The server group to which the job is assigned. Only servers in the specified server group will work on the given job, unless the group is set to use idle non-group servers.

## 3. The Backburner Manager can send job success, failure and other notifications to the email addresses you specify in the Notifications area.

Item	Description
Enable Notifications	Turns on/off notifications for the job.
Notify Failures	Enable to be notified on job failure.
Notify Progress	Enable for notification by email as each render node completes its block of tasks.
Notify Completion	Enable for email notification on job completion.
Notify Progress Every Nth Task	Enable for email notification when each <i>n</i> th task is completed.

Item	Description
Send Emails	Enable email notification. To receive email notifications, both this checkbox and the Enable Notifications checkbox must be enabled.
Alert Email From	Return address used by the Backburner Manager when sending notification email.
Alert Email To	Destination address.
Alert Email Server	Server where the smtp mailer daemon is running.

- Assign new servers to the job, or remove servers from the job using the Add and Remove buttons in the Servers area.
- Set job dependencies using the Add and Remove buttons in the Job Dependencies area.  
The current job will be started only when all the jobs in the Current Dependencies list are complete.
- Apply your changes.

Item	Description
Apply	Changed settings apply to new tasks only. Completed tasks are not reprocessed.
Apply & Restart	All completed work is discarded and the job is reprocessed in its entirety, using the new settings.

## Restarting Jobs

Use the following procedure to restart jobs.

### To restart a job:


- On the Jobs tab, click the Restart button next to the job of interest.
- Confirm the action in the pop-up dialog that appears.  
The selected job is restarted and its icon changes to green. If another job is already being processed, the selected job becomes pending, and its icon turns white.

## Cloning Jobs

Use the following procedure to clone a job.


**To clone a job:**

1. On the Jobs tab, click the Clone button next to the job of interest.



2. Confirm the action in the pop-up dialog that appears.

The job is duplicated and its clone appears at the top of the Job list with the same name and job status. The description field indicates the job is a clone.



3. Modify job settings for the clone, as desired. See [“Modifying Job Settings”](#) on page 60.

The job settings for a clone are identical to those of its parent job. You can modify these settings to customize how the clone is to be processed by the system.

4. Depending on the status of the clone, you may wish to take further action, as indicated in the following table.

Status	Suggested Action
Pending	Allow the job to be processed following the normal sequence of events. No action necessary.


Status	Suggested Action
Suspended	Restart or reactivate the job. See <a href="#">“Suspending and Reactivating Jobs”</a> on page 59.
Completed	Restart the job. See <a href="#">“Restarting Jobs”</a> on page 63.

## Archiving Jobs

Use the following procedures to archive a job, restore an archived job, or delete a job from the archive. Jobs can be archived automatically, when the manager has been configured to do so. You can also archive jobs directly from the monitor, as explained here. Note that archiving a job has no effect upon the associated media. The job archive contains job metadata only; that is, it contains the information needed to restart a job, but not the source media.

**To archive a job:**

1. On the Jobs tab, begin by clicking the Suspend button next to the job of interest.  
Jobs are archived (and restored) with their original status intact. Suspending the job before archiving it minimizes the impact on the system if the job is restored later.
2. Once the job is suspended, click the Archive button.



3. When prompted, click OK.

The job is archived and removed from the Job list. By default, archived jobs are saved to the *Network\Archive* folder where the Backburner Manager is installed.

BACKBURNER

Autodesk

Jobs Servers Server Groups Archives About

Search For  By Column  Refresh

Job Name	Status	Progress	Tasks	Priority	Submitted	Started	Plugins	Owner	Controls
burn_ssdau_060514_17.44.21.13	Not Started	0 %	0 / 70	50	06/13/2006 at 05:44:24 PM Unknown	burn 2007	burn 2007	fame2007	Suspend Restart Close Archive Settings Delete
burn_ssdau_060513_17.44.11	Not Started	100 %	70 / 70	50	06/13/2006 at 05:44:15 PM 06/14/2006 at 10:06:51 AM burn 2007	burn 2007	fame2007	Suspend Restart Close Archive Settings Delete	
burn_ssdau_060513_17.45.39	Suspended	0 %	0 / 70	50	06/13/2006 at 05:16:40 PM Unknown	burn 2007	burn 2007	fame2007	Activate Restart Close Archive Settings Delete
burn_ssdau_060513_17.13.43	Active	71 %	50 / 70	50	06/13/2006 at 05:13:43 PM 06/14/2006 at 10:06:08 AM burn 2007	burn 2007	fame2007	Suspend Restart Close Archive Settings Delete	
burn_ssdau_060513_16.53.48	Complete	100 %	70 / 70	50	06/13/2006 at 04:53:47 PM 06/14/2006 at 10:02:18 AM burn 2007	burn 2007	fame2007	Restart Close Archive Settings Delete	
burn_ssdau_060513_16.25.09	Suspended	0 %	0 / 70	50	06/13/2006 at 04:25:10 PM Unknown	burn 2007	burn 2007	fame2007	Activate Restart Close Archive Settings Delete
burn_ssdau_060513_16.05.09	Suspended	0 %	0 / 70	50	06/13/2006 at 04:09:01 PM Unknown	burn 2007	burn 2007	fame2007	Activate Restart Close Archive Settings Delete
burn_ssdau_060513_16.04.31	Active	0 %	0 / 70	40	06/13/2006 at 04:04:31 PM 06/14/2006 at 10:14:35 AM burn 2007	burn 2007	fame2007	Suspend Restart Close Archive Settings Delete	
burn_ssdau_060514_09.37.37	Complete	100 %	100 / 100	50	06/14/2006 at 09:37:19 AM 06/14/2006 at 09:37:18 AM burn 2007	burn 2007	fame2007	Suspend Restart Close Archive Settings Delete	
burn_ssdau_060514_09.13.12	Complete	100 %	100 / 100	50	06/14/2006 at 09:11:13 AM 06/14/2006 at 10:02:29 AM burn 2007	burn 2007	fame2007	Restart Close Archive Settings Delete	

- To view the list of archived jobs, click the Archives tab.

The Job Archive page appears, presenting information for all archived jobs.

Job	Owner	Description	Type	Date submitted	Date completed	Actions
burn_ssdau_060514_09.37.38	fame2007	CW_2k_10_new	burn 2007.0 v 300	06/14/2006 at 09:37:38 AM	06/14/2006 at 10:10:49 AM	Activate Delete
Wire_06-05-10_16.08.50	root	*	Wire v 300	05/10/2006 at 02:58:43 PM	05/10/2006 at 05:14:58 PM	Activate Delete
Wire_06-05-10_16.08.55	root	*	Wire v 300	05/10/2006 at 02:58:43 PM	05/10/2006 at 05:15:04 PM	Activate Delete
burn_ssdau_060516_16.56.04	Root2007	None	burn 2007.0 v 300	05/10/2006 at 04:56:08 PM	05/10/2006 at 04:57:19 PM	Activate Delete
burn_ssdau_060505_17.30.53	braten	Clip: NOISE	burn 2007.0 v 300	05/05/2006 at 05:30:53 PM	05/05/2006 at 05:31:30 PM	Activate Delete
Wire_06-05-10_16.08.45	root	*	Wire v 300	05/10/2006 at 02:58:43 PM	05/10/2006 at 05:14:37 PM	Activate Delete
Wire_06-05-10_16.08.13	root	*	Wire v 300	05/10/2006 at 02:56:43 PM	05/10/2006 at 05:07:05 PM	Activate Delete
Wire_06-05-10_16.07.06	root	*	Wire v 300	05/10/2006 at 02:56:43 PM	05/10/2006 at 05:15:44 PM	Activate Delete
Wire_06-05-10_16.07.04	root	*	Wire v 300	05/10/2006 at 02:56:43 PM	05/10/2006 at 05:15:33 PM	Activate Delete
Wire_06-05-10_16.04.05	root	*	Wire v 300	05/10/2006 at 02:58:43 PM	05/10/2006 at 04:43:29 PM	Activate Delete
Wire_06-05-10_16.01.07	root	*	Wire v 300	05/10/2006 at 02:58:43 PM	05/10/2006 at 04:38:07 PM	Activate Delete
Wire_06-05-10_16.07.09	root	*	Wire v 300	05/10/2006 at 02:58:43 PM	05/10/2006 at 05:15:55 PM	Activate Delete
Wire_06-05-10_16.07.18	root	*	Wire v 300	05/10/2006 at 02:58:43 PM	05/10/2006 at 05:16:30 PM	Activate Delete

**To restore or delete a job from the archive:**

- Click the Archive tab.

The Job Archive appears, presenting information for all archived jobs.



- Find the job of interest, then perform the desired action, as explained in the following table.

Action	Result
Delete	Removes the job from the archive. Since deletion cannot be undone, you are asked to confirm your action.
Activate	Restores a selected job to the job queue, removing it from the archive. You can then choose to modify its settings and restart the job. Jobs reappear in the job queue with the settings they had when archived. This includes job status. If a job was suspended or completed when it was archived, once restored you must re-activate or restart it to start the processing again.
Refresh	Updates the display with the most recently archived jobs.

- Once finished, return to the Job List page by clicking the Jobs tab.


## Deleting Jobs

Use the following procedure to delete jobs from the job queue.

**NOTE:** Deleting cannot be undone. If you think you may need to run the job again in the future, or examine job details, consider archiving it instead. See [“Archiving Jobs”](#) on page 65.

### To delete a job:

- On the Jobs tab, click the Delete button next to the job of interest.



- When prompted, click OK.  
The job is deleted from the system and removed from the Job list.



# Managing Render Nodes – Web

## Summary

<a href="#">Overview</a> .....	69
<a href="#">Monitoring Render Nodes</a> .....	69
<a href="#">Shifting Nodes Between Jobs</a> .....	72
<a href="#">Deleting Offline Render Nodes</a> .....	74
<a href="#">Setting Render Node Availability</a> .....	75
<a href="#">Working with Server Groups</a> .....	76

## Overview

The procedures in this chapter relate to managing the render farm at the level of its render nodes, using the Backburner Web Monitor.

**NOTE:** If the Backburner Web Monitor returns an error message indicating “queue control is needed for the requested operation,” it indicates a Backburner *Windows* Monitor is already connected to the Backburner Manager. To obtain queue control, disconnect the Backburner Windows Monitor from the manager. For a more complete discussion, see [“Obtaining Queue Control”](#) on page 14.

## Monitoring Render Nodes

Use the following procedure to monitor the status of render nodes.

### To view render node status:

1. Launch a web browser and log in to the Backburner Web Monitor. See [“Backburner Web Monitor”](#) on page 16.
2. Click the Servers tab.

The Server list appears, showing all render nodes on the system.

Server Name	Current Job	Status	Available Disk Space	Memory	Controls
huan11	Burn_solides_060613_16.53.46	Busy	28.3 GB	3017 MB	Settings
huan12	Burn_solides_060613_16.53.46	Busy	28.0 GB	3017 MB	Settings
huan13	Burn_solides_060613_17.13.43	Busy	28.4 GB	2868 MB	Settings
huan14	Burn_solides_060613_16.04.31	Busy	68.2 GB	4005 MB	Settings
huan1	Burn_solides_060613_13.37.40	Busy	13.5 GB	2524 MB	Settings
huan5	Burn_solides_060613_17.13.43	Busy	12.8 GB	2524 MB	Settings
huan6	None	Error	13.3 GB	2524 MB	Settings
com1	None	Absent	63.0 GB	3017 MB	Settings Delete
huan	None	Idle	0.7 GB	3072 B	Settings
quade	None	Absent	24.3 GB	3017 MB	Settings Delete
valletta	None	Idle	62.3 GB	3871 MB	Settings

The icon beside each server provides a visual indication of its state.

Icon Color	State
Green	OK
Yellow	Idle
Grey	Absent
Red	Error

**NOTE:** If a server that is already known to the Backburner Manager subsequently fails to re-connect to it, the manager marks it as *absent*. For more information, see [“Deleting”](#) on page 23.

This list shows the following information for each node.

Column	Description
Server Name	Server name (host name).
Current Job	The current job as assigned by the Backburner Manager.
State	Current server activity, as explained in the table above
Available Disk Space	Disk space available for rendering.
Memory	Installed RAM.
Controls	Users with administrator privileges see a complete set of controls. Otherwise, the set is more restricted.

- Click on a render node of interest to view its details.

The screenshot displays the Autodesk Backburner application window. The 'Servers' tab is selected, showing a list of servers. The server 'burn1' is highlighted, and its details are shown in the main pane. The 'Current Job' is 'Burn\_splden\_000014\_14.16-54', the 'Status' is 'Busy', 'Available Disk Space' is '12.5 GB', and 'Memory' is '2524 Mb'. Below this, the 'Server properties' section lists: User: root, IP address: 172.17.20.64, Computer Name: burn4, Platform: Red Hat Enterprise Linux WS release 4 (Nahant Update 2), # of CPUs: 2, and Perf Index: 1.0. The 'Module Info' section lists details for the Server, Backburner API, Plugin, and Command Line Tool. The 'Schedule' section shows a calendar view for the week of Sunday, January 12, to Saturday, January 18, 2008, with a grid of checkboxes for each hour of the day.

Item	Description
<b>General Area</b>	
Current Job	The current job as assigned by the Backburner Manager.
Status	Current server activity.
Available Disk Space	Disk space available for rendering.
Memory	Installed RAM.
<b>Server Properties</b>	

Item	Description
User	User account name under which the Backburner Server was launched.
IP address	The server's IP address. This is used by the Backburner Manager to communicate with the server.
Computer Name	Server host name.
Platform	Operating system details.
# of CPUS	The total number of CPUs installed on the system.
Perf. Index	A value in the range [0–1] indicating the performance level of the render node, relative to the other servers on the same job. A score of 1 indicates this is the best-performing server.
<b>Module Info</b>	
Server	Backburner Server software version.
Backburner API	DSO version. Should match the Backburner software version.
Plugin	A list of adapters installed on the render node, for example: <ul style="list-style-type: none"> <li>• Burn: The Burn renderer.</li> <li>• mio: The Media I/O adapter used by WiretapCentral.</li> <li>• Command Line Tool: The adapter associated with cmdjob.</li> </ul>
Schedule	The render node's availability schedule. See <a href="#">“Setting Render Node Availability”</a> on page 75.

4. Click Servers to return to the list of nodes.


## Shifting Nodes Between Jobs

Use the following procedure to shift a render node from one job to another.


**NOTE:** You can also assign a node to a job from the Jobs tab. See [“Modifying Job Settings”](#) on page 60.

**To shift a render node:**


1. On the Servers tab, click on the Settings button next to the node you want to reassign.



Settings for the server appear in the monitor.




- Free up the node by selecting all jobs in the Assigned Jobs list and clicking Remove.



The node ends its current processing task and becomes available for other jobs.

- In the Available Jobs list, select the job to which you want to assign the node and click Assign.



- Apply your changes.  
The render node is assigned to the new job. When the node ends its current task, it begins working on the newly assigned job.
- Click the Servers tab to return to the list of all servers.

## Deleting Offline Render Nodes

Use the following procedure to delete offline render nodes from the system. Deleting a render node removes its entry from the database maintained by the Backburner Manager. It does not delete any software from the node itself.

### To delete a render node:

- On the Servers tab, click on the Delete button next to the node of interest.  
Only nodes marked by the system as *absent* can be deleted.
- Locate the render node to be removed and click the Delete button.  
You are prompted to confirm the deletion of the node from the list.  
The node is deleted and removed from the list.




# Setting Render Node Availability

Use the following procedure to schedule the availability of a render node.

## To schedule the availability of a render node:

1. On the Servers tab, click on the Settings button next to the node of interest.  
Settings for the server appear in the monitor.
2. Locate the node whose availability is to be changed and click its Settings button.



Settings for the render node appear. In the Schedule area, enabled checkboxes indicate the node is available to process jobs. By default, nodes are always available.



3. Fill the checkboxes to make the node available:
  - Select a single hour by filling just the one checkbox.
  - Fill the same hour for each day with one click using the hour buttons.
  - Fill a whole day by using the days -of-the-week buttons.

The following schedule shows a render node that is available weekdays at night and 24 hours a day on weekends. This might be the case for a creative workstation used as a render node after-hours, for example.

4. Apply your changes.

## Working with Server Groups

Use the following procedures to create or delete a named collection of render nodes, called a *server group*, and to assign a server group to a job.

**NOTE:** For information on configuring a creative application to submit jobs to a server group, see the User Guide for application of choice. To configure a Visual Effects and Finishing application to submit its jobs to a server group, set the optional *BackburnerManagerGroup* keyword in the application's *init.cfg* file. For more information see the *Burn Installation and User Guide*.

### To create a server group:

1. On the Servers Groups tab, enter a name for the new server group in the Group Name field and click the Add button.

Group Name	Number of Servers	Use like Non-Group Servers	Suspend Active Non-Group Jobs	Weight	Controls
another_group	2	No	No	N	Settings Delete
groups_2006	2	No	No	N	Settings Delete
hicks_group	3	No	No	N	Settings Delete

A new page appears, where you can configure the server group and assign render nodes to it.



2. Configure the behaviour of the group as desired.


Item	Description
Rename Group	The name of the server group as it will appear in the UI.
Can Use Idle Non-group Servers	Enable to allow the Backburner Manager to temporarily assign idle non-group render nodes to the group. Enabling this option increases the rendering power of the group.
Suspend Non-Current Group Jobs	Enable to allow the Backburner Manager to suspend the processing of non-group jobs running on group nodes, when a new job is submitted to the group. Enabling this option allows a render node group to automatically switch from non-group jobs to new group-jobs.
Weight	Adjusts the priority of jobs assigned to the server group. Jobs assigned to a high-weight server group are given higher priorities than jobs assigned to lower-weight groups. In fact, a job assigned to a high-weight group may be rendered ahead of non-group jobs—even if the non-group jobs have higher priorities at the job-level.

3. Add render nodes to the group by selecting them in the *Available Servers* list and clicking Add Server.

The render nodes are added to the group.

4. Once you are satisfied with your choices, click Apply to commit the changes.


The new server group is added to the list.




**NOTE:** Server groups you create in the Backburner Web Monitor appear as *global* groups in Backburner Windows Monitor.

**To assign a server group to a job:**


1. On the Jobs tab, click the Settings button next to the job of interest.



Settings for the job appear in the monitor.



2. (Optional) In the Servers area remove any nodes currently assigned to the job using the Remove button.
3. In the Job Properties area, select a server group from the Server Group pulldown list.



## 4. Apply your changes.

Item	Description
Apply	Changed settings apply to new tasks only. Completed tasks are not reprocessed.
Apply & Restart	All completed work is discarded and the job is reprocessed in its entirety, using the new settings.

Note:

- If nodes in the group are busy, they complete their currently-assigned jobs before working on the new job to which you have assigned them. Otherwise, they begin working on the new job immediately.
- If the “Suspend current non-group jobs” option is enabled for the server group, all nodes in the server group drop their current rendering job and begin processing the assigned job immediately.

**To delete a server group:**

1. On the Server Groups tab, click the Delete button next to the server group of interest.

2. When prompted to confirm your action, click OK.

The selected server group is deleted.

3. When prompted, click OK.

The group is deleted from the Server list. The render nodes themselves remain untouched, and can be assigned to other groups, as needed.

# Additional Windows Interfaces

## Summary

<a href="#">Overview</a> .....	81
<a href="#">Backburner Manager – Windows</a> .....	82
<a href="#">Backburner Server – Windows</a> .....	82

## Overview


The Backburner Monitor described throughout this guide is often the only “visible” component of Backburner—that is, the only component with a GUI. In a Windows installation, the Backburner Manager and Backburner Server can also have GUIs. If these have been configured to run as Windows services, they run unobtrusively in the background. No GUIs are displayed. However, if these run as regular applications, they will be visible. This chapter provides an overview each GUI.

Both the manager and server interfaces are simple text windows in which startup, information, and error messages are displayed. By default the messages are also written to log files. There are two dialogs available from menus for configuring behaviour, and log levels, respectively. In both cases, settings you make using the dialogs are saved in the Backburner configuration file, *backburner.xml*, on the machine where the component is running. You can also edit this file directly.

For details, see the *Backburner Installation Guide*.


## Backburner Manager – Windows

The following illustration identifies the Backburner Manager GUI.



## Backburner Server – Windows

The following illustration identifies the Backburner Server GUI.





# Advanced Operations

## Summary

[Submitting Jobs from a Command Line or Script](#) ..... 83

## Submitting Jobs from a Command Line or Script

Use the Backburner *cmdjob* command line plug-in to submit batch, executable, or script files to Backburner as “custom” jobs. This tool provides flexibility in running custom jobs from scripts. For example, you could create a script that submits all jobs contained in a network folder to be rendered automatically at night.



**WARNING:** Special security consideration should be given to the *cmdjob* utility, as it can execute commands remotely on all the Render Nodes on the network. A trained systems administrator should ensure that the execution permissions are properly set and managed.

## Using the *cmdjob* Utility

Use the following procedure to submit jobs to Backburner using the *cmdjob* utility.

### To use the *cmdjob* utility:

1. Open a DOS shell or Linux terminal and navigate to the *Backburner* folder.

Operating System	Location of the Backburner Folder
Windows	C:\Program Files\Autodesk\Backburner
Linux	/usr/discreet/backburner

2. Submit a job or jobs to the *cmdjob* utility using the following syntax:

**cmdjob** <options> <executable\_to\_run> <parameters>

Refer to the following sections for help with the options and parameters you can specify, as well as for information on tokens:

- [“Options for the cmdjob Utility”](#) on page 84
- [“Parameters for the cmdjob Utility”](#) on page 85

- [“Tokens for the cmdjob Utility”](#) on page 86

You can use options, parameters, and tokens at the command line of a DOS shell or Linux terminal as well as in a batch file or script. Note the following:

- Options, parameters, and tokens are not case-sensitive.
- If multiple occurrences of the same option or parameter are used, only the last occurrence is processed by the *cmdjob* utility.

## Options for the *cmdjob* Utility

This section describes the options you can use with the *cmdjob* command.

### Options

Option	Description
-?	Displays the help for the <i>cmdjob</i> utility.
-cmdFile:<file>;<file>... or @<file>;<file>...	Specifies one or more text files that contain options to the <i>cmdjob</i> utility.

### Job Options

Option	Description
-jobName:<name>	Sets the job name. The default is "cmdJob".
-description:<string>	Defines a description of the job.
-priority:<number>	Sets the job priority. The default value is 50. The other values are either 0 (Critical) or 100 (Suspended).
-workPath [folder]	Working folder or directory for the <i>cmdjob</i> utility. The default value is "...\\backburner\\Network\\ServerJob" folder. This path is set before the <i>cmdjob</i> utility interprets processing options for a job. This path is also set as the working path for servers. If the working folder is not set, the full path to the executable and target files must be specified when submitting the job.
-logPath:<folder>	Specifies the location of the folder or directory in which the task logs are created. This location must specify an existing folder since the command line utility cannot create this folder if it does not exist. This option is disabled by default.
-showOutput<file>;<file>;...	Makes the specified output files accessible from the Backburner Monitor or Web Monitor.

## Job Submission Options

Option	Description
- dependencies:<jobname>;< jobname>;<jobname>;...	Defines a list of job dependencies.
-timeout:<minutes>	Number of minutes before a task time-out should occur. Default value is 60 minutes.
-attach	Attaches the batch file to the job as a .zip file. The batch file is then extracted on each machine before the job is processed.
-progress	Shows the progress of the job in the shell as it is being processed.
-suspended	Sets the status of the job to suspended.

## Network Options

Option	Description
-manager:<name>	Sets the name of the manager. The default is an automatic search.
-port:<number>	Sets the port number.
-servers:<server>;<server>;...	Defines the set of servers to which the job is submitted. Ignored if a server group is specified using -group.
-serverCount:<number>	Sets the maximum number of servers that can simultaneously work on the job.
-group:<string>	Defines the server group to which the job is submitted.

## Notification Options

Option	Description
-emailFrom:<address>	Sets the source email address for notification emails.
-emailTo:<address>	Sets the destination email address for notification emails.
-emailServer:<server>	Sets the name of the SMTP email server Backburner uses to send notification emails.
-emailCompletion	Sends a notification email when the job is completed.
-emailFailure	Sends a notification email if the job fails.
-emailProgress:<number>	Sends a notification email when the number of tasks that you set are completed.

## Parameters for the *cmdjob* Utility

This section describes the options you can use with the *cmdjob* command.

Option	Description
-taskList:<file>	Sets the task list file. The file contains a tab-separated table. Use fill-in tokens to reference the table.
-taskName:<number>	Sets the task name column in the task list file. A value of 0 means this column is unnamed while a value greater than 0 specifies the column in the file for the task names. This is used for feedback in the monitor when looking at the task list.
-numTasks:<number>	Sets the number of tasks for the job. This option is ignored if -taskList is used.
-tp_start:<number>	Sets the starting offset of the default task parameter in numeric format. Ignored if -taskList specified.
-tp_jump:<number>	Sets the increment of the default task parameter in numeric format. Ignored if -taskList used.
-jobParamFile:<file>	Sets the job parameter file. See example below.

## Tokens for the *cmdjob* Utility

A token is a reference to a value that can vary. It is evaluated on the server assigned to the job at the time the *cmdjob* utility executes. You cannot nest tokens within tokens.

Option	Description
%dsc	Job description.
%srv	Name of the server executing the task.
%tpX	Task parameter X from the task list where X is the column index in the task list file.
;%*tpX	Same as %tpX where * indicates the number of 0 padded digits to use.
%tn	Task number of the assigned task.
;%*tn	Same as %tn where * indicates the number of 0 padded digits to use.
%jpX	Parameter X from the job parameter file where X is the row index in the job parameter file.
;%*jpX	Same as %jpX where * indicates the number of 0 padded digits to use.



# Troubleshooting Backburner

## Summary

<a href="#"><i>Basic Troubleshooting Techniques</i></a> .....	87
<a href="#"><i>Common Problems</i></a> .....	88
<a href="#"><i>Verifying Communication Between Two Hosts</i></a> .....	91
<a href="#"><i>Verifying the Packet Size</i></a> .....	92
<a href="#"><i>Configuring Backburner Log Files</i></a> .....	92
<a href="#"><i>Editing the backburner.xml File</i></a> .....	96
<a href="#"><i>Resolving a Host Access Error</i></a> .....	97
<a href="#"><i>Resolving Invalid DNS Addresses</i></a> .....	98
<a href="#"><i>Resolving a Problem Connecting to the Backburner Manager</i></a> .....	98
<a href="#"><i>Adding the Backburner Path to the Windows Path Environment Variable</i></a> ..	100
<a href="#"><i>Resolving Network Card Priority</i></a> .....	101
<a href="#"><i>Resolving an Unavailable Render Node Problem</i></a> .....	102
<a href="#"><i>Restarting Suspended Render Nodes</i></a> .....	104
<a href="#"><i>Resolving a Render Node Failure</i></a> .....	104
<a href="#"><i>Adjusting the Maximum Number of Render Nodes Per Job</i></a> .....	104

## Basic Troubleshooting Techniques

Troubleshooting problems on a Backburner network can be difficult because of the different hardware and software platforms that a Backburner network may cover. If you experience problems, start by checking the following issues first:

- All hosts on the Backburner network can communicate with each other. See [“Verifying Communication Between Two Hosts”](#) on page 91.
- If you are sending jumbo frames, verify that each host can handle that packet size. See [“Verifying the Packet Size”](#) on page 92.
- Any shared resources are both visible and accessible to all hosts on the Backburner network.

Make sure the folders containing images and models used for your jobs are shared by all hosts on the Backburner network. If Backburner is also rendering jobs from Autodesk applications that run on a Linux platform, make sure that directories are visible from all hosts on the Backburner network, and that they have the appropriate permissions set.

- Any plug-ins, fonts, and codecs necessary for rendering jobs are installed on each render node.
- Licensing (where required) is properly configured for each host.

If Backburner is also rendering jobs from Autodesk applications that run on a Linux platform, make sure the License Server for the network is functioning and that the licenses can be checked out.

Log files are also a useful source of information for troubleshooting a problem. Both Backburner Manager and Backburner Server maintain log files, and you can define the types of events you want these files to record. See [“Configuring Backburner Log Files”](#) on page 92 for an explanation of these files and the information they contain.

## Common Problems

This section describes common problems in a Backburner network that uses Linux or Windows render nodes, and provides suggestions on how to solve these problems. For additional help with problems on a Backburner network using Burn render nodes, see the *Autodesk Burn Installation and User Guide*.

### Problems on Startup

These problems can occur when you start Backburner Manager or Backburner Server on Linux or Windows systems.

Problem	Common Cause
An <code>Application Terminated</code> error appears in the Backburner Monitor or the Backburner Web Monitor.	An incorrect IP address for the Backburner Manager, incorrect port numbers for the Manager and/or Server, incorrectly configured TCP/IP information. See <a href="#">“Resolving a Host Access Error”</a> on page 97.
A <code>Host Not Found</code> error appears when starting Backburner Server on a Windows system.	An incorrect IP address for the Backburner Manager, incorrect port numbers for the Manager and/or Server, incorrectly configured TCP/IP information. See <a href="#">“Resolving a Host Access Error”</a> on page 97.
An <code>Overlapped I/O Operation is in Progress</code> error appears when starting Backburner Server as a Windows service.	The Backburner Server service is already running. This is not a problem. You can continue with network rendering.

Problem	Common Cause
A Service is Installed. Cannot run Server Application. error appears when starting Backburner Server on a Windows system.	The Backburner Server service is installed and running. You can continue with network rendering without launching the Backburner Server application.
An Error registering to <server_name> error appears when starting Backburner Manager or Server on a Windows system.	Invalid IP addresses in the DNS Search Order, or the Primary or Secondary WINS Server in the Microsoft TCP/IP dialog. See <a href="#">"Resolving Network Card Priority"</a> on page 101.
A Cannot handle registration from <server_name>. Will try later. error appears when starting Backburner Manager or Server on a Windows system.	The number of concurrent TCP sessions currently exceeds the limit the Manager can handle. Servers automatically retry, usually within a minute, so the problem should resolve itself.
A Cannot access job share <server_name>. Requesting archive directly. error appears when starting Backburner Server on a Windows system.	This warning may appear only on Backburner networks and can be disregarded. The warning appears when a required folder and/or drive is not shared using Windows file sharing. If this occurs, Backburner switches to TCP/IP to access the required folder and/or drive across the network. You can prevent this warning from appearing by ensuring all network components share the same folders and drives.
An Invalid name or TCP/IP subsystem not installed error appears when starting Backburner Manager or Backburner Server on a Windows system.	The TCP/IP protocol is not running or not working properly. This error may occur on workstations where a pre-installed version of Windows includes a misconfigured TCP/IP protocol. Remove and then reinstall the TCP/IP protocol and reboot the workstation. Once the workstation has rebooted, see <a href="#">"Verifying Communication Between Two Hosts"</a> on page 91 to ensure that it can communicate with other network components.

## Problems Submitting Jobs

These problems can occur when you attempt to submit a job to the Backburner network on Linux or Windows systems.

Problem	Common Cause
The Backburner Manager is unavailable when submitting jobs.	An incorrect IP address or an IP address that connects to the wrong Backburner Manager, a Backburner Manager that is not running or is hung, or communication problems between the Backburner Manager and the render nodes. See <a href="#">“Resolving a Problem Connecting to the Backburner Manager”</a> on page 98.
An <code>Unknown error loading application</code> error appears in the Backburner Manager or Monitor when submitting jobs to Backburner on a Windows system.	The path to Backburner is not defined in the <i>Path</i> environment variable. See <a href="#">“Adding the Backburner Path to the Windows Path Environment Variable”</a> on page 100.

## Problems with Render Nodes

These problems can occur with a render node or the jobs sent to it on Linux or Windows systems.

Problem	Common Cause
A render node appears unavailable in the Backburner Monitor or Web Monitor.	The workstation is offline, the Backburner Server is not running or is hung, the Server is not using the correct IP address for the Manager, or the Manager cannot communicate with the Server. See <a href="#">“Resolving an Unavailable Render Node Problem”</a> on page 102.
A render node is idle and cannot connect to the Backburner Manager.	Check the render node to make sure that the IP address for the Manager is correct. Other networking devices such as a second network card, or wireless device connected through a USB port may cause problems. See <a href="#">“Resolving Network Card Priority”</a> on page 101.
A <code>Cannot network render. Backburner not found or not installed.</code> error appears in the application when a job is sent for rendering on a Windows system.	Either Backburner is not installed or its path is not defined in the <i>Path</i> environment variable. Verify that Backburner is installed and/or see <a href="#">“Adding the Backburner Path to the Windows Path Environment Variable”</a> on page 100.
A render node remains suspended even while jobs are being processed by Backburner.	The render node is unavailable. See <a href="#">“Restarting Suspended Render Nodes”</a> on page 104.
A render node fails when a job is assigned to Backburner.	Render nodes can fail during a network render job for a variety of reasons, some of the most common ones being incorrect paths, missing plug-ins, fonts, or codecs, or insufficient disk space. See <a href="#">“Resolving a Render Node Failure”</a> on page 104.



Problem	Common Cause
An Unknown TCP gibberish from <Backburner_Manager_IP address_or_hostname> error appears in Backburner Server.	There is not enough free disk space on the render node, the connection between Backburner Manager and Backburner Server is bad, or network drivers are not working properly. Check the amount of free disk space on the render node and resubmit the job, if this is sufficient. If the problem reoccurs, check the drivers used for the network card and TCP/IP protocol as well as the physical network connection to the render node.
A Task Error: The filename, directory name, or volume label syntax is incorrect (0x7b) error appears in the log file of Backburner Server.	This error occurs when the output folder or directory name is misspelled or contains invalid characters. Check the output details for the job in the Backburner Monitor and correct the output folder name or path to fix this problem.
Only a single render node can be assigned to a job.	The output of the job is not an image sequence (for example, it is an AVI or MOV file). A job that does not produce an image sequence can only be assigned to a single server. Note that if such a job is stopped for any reason (to deactivate it or because the server goes down), re-rendering the file restarts at the first frame. Frames cannot be appended later to these file types. You can change which server a single-server job uses by removing the current server from the job, and then adding a different one.
No additional render nodes can be assigned to a job, even if render nodes are available.	The maximum number of render nodes per job is reached. You can change this maximum number to avoid this problem. See <a href="#">“Adjusting the Maximum Number of Render Nodes Per Job”</a> on page 104. However, changing these settings is not recommended. Increase these values only if you are sure that there is sufficient slack in your Backburner network.

## Verifying Communication Between Two Hosts

Use the **ping** command to test communication between hosts, for example between a render node and a Backburner Manager on Linux or Windows systems.

Use:	To:
<b>ping</b> <ip_address>	Verify that the host on which you issue the command can communicate with the host whose address you specify in <ip_address>. Example: <b>ping 132.22.34.15</b> If this command does not return a response from the host whose IP address you specified, ensure there is a valid network connection, and that both machines are on the same network.
<b>ping</b> <hostname>	Verify that the host on which you issue the command can communicate with the host whose name you specify in <hostname>. Example: <b>ping managerhost</b>

**NOTE:** If you can successfully “ping” the IP address, but not the hostname, the Domain Name Server may be unable to map the hostname to an IP address. Or, if you are running the command on a Linux workstation, the hostname/IP address pair may be missing from the `/etc/hosts` file or from the NIS (Network Information Services) server. If necessary, consult your network administrator for help correcting the missing hostname.

## Verifying the Packet Size

You can use the **ping** command to determine the packet size a host can accept on Linux or Windows systems.

Use:	To:
<b>ping -s</b> <packet_size> <hostname>	Verify that the host can handle the packet size it is being sent. Example: <b>ping -s 50000 managerhost</b>

If the host can handle regular packet size, but not oversize packets, your jumbo frame may be incorrectly configured, the switch may not support jumbo frames, or one of the ports (either the switch or the adapter) may not be set for jumbo frames. If you are not sure whether your system is using jumbo frames, consult your network administrator.

## Configuring Backburner Log Files

Both Backburner Manager and Backburner Server maintain log files. The information in these log files can be useful when you are troubleshooting problems with the Backburner network. For example, you can consult the files to determine when the Backburner Manager or Server was started, when Backburner Servers on a network were shut down, and whether any errors occurred that halted the rendering of a job.

The log files are stored in `/usr/discreet/backburner/Network` on Linux. On Windows, they are stored in a `/backburner` subdirectory of the per-user application data directory. For example, `C:\Documents and Settings\<user>\Local Settings\Application Data\backburner`, in Windows XP.

**NOTE:** Running the Backburner Manager or Backburner Server as a Windows service changes the location of the `backburner.xml` and log files to `/backburner` subdirectories of the per-user application data directory subdirectories belonging to the *Local Service* user. These directories are hidden to non-administrative level users. For example, on Windows XP:

`C:\Documents and Settings\Local Service\Local Settings\Application Data\backburner\backburner.xml`


You can adjust system parameters and define the events and information that Backburner Manager or Backburner Server records in its log file by editing the `backburner.xml` file. Additionally, on Windows systems you can adjust the log file settings through an application dialog.

#### To configure Backburner log file settings on Windows systems:

1. Start the Backburner Manager or Server. Refer to the *Autodesk Backburner Installation Guide* for help starting these applications.

**NOTE:** You cannot configure log file settings for Backburner Manager or Backburner Server while these applications are running as Windows services.

2. From the Edit menu, choose Log Settings.  
The Logging Properties dialog appears.



Use this dialog to set the events shown in the application's window or logged to its log file.

- The Log To Screen options set events that are displayed in the Backburner Manager or Server application window.
  - The Log To File options set events that are saved to the Backburner Manager or Server log files. These are usually the same messages that appear on the screen.
3. Enable options in the dialog to determine the messages that are saved to log files. See [“Specifying Backburner Log File Contents”](#) on page 95.

By default, the following events are always logged to the screen and to the log files:

- Error
- Warning
- Info

Enabled events are saved to the *backburner.log* file for Backburner Manager and to the *backburnerServer.log* file for Backburner Server.

4. In the Buffer Limit field, specify the maximum size of the buffer holding the messages.
5. Click Clear Log to clear the buffer holding messages in the application window.
6. Click Clear Log File to clear the contents of the *backburner.log* or *backburnerServer.log* file.

**NOTE:** Log files are cleared only when you click the Clear Log File button. Otherwise, the size of these files continues to grow with each job rendered.

#### To configure Backburner log file settings by editing the *backburner.xml* file:

1. Stop Backburner Manager and/or Backburner Server.
2. Locate the *backburner.xml* file:
  - Linux: */usr/discreet/backburner/Network*
  - Windows: In the *\backburner* subdirectory of the per-user application data directory. For example, *C:\Documents and Settings\<user>\Local Settings\Application Data\backburner*, in Windows XP.
3. Edit the *backburner.xml* file using an XML or text editing application.
4. Under the `<LogCfg>` heading, enable or disable the options to determine the messages that are saved to log files. See [“Specifying Backburner Log File Contents”](#) on page 95. The settings are enabled with a “1” and disabled with a “0”.
5. Save and exit the *backburner.xml* file.

6. Restart Backburner Manager or Backburner Server. Refer to the *Autodesk Backburner Installation Guide* for help starting these applications.

**NOTE:** Any changes made to the *backburner.xml* file take effect only when the Backburner Manager or Backburner Server is restarted.

The new log file settings take effect.

## Specifying Backburner Log File Contents

The information and type of events that can appear in the Backburner Manager or Server, or be written to their log files, are defined as follows.

**Error** — Fatal errors that halt the rendering of a job. These messages are preceded by a red “ERR”, label and include the following events:

- Failed Renderings and Frame Errors
- Backburner Server runs out of memory
- Backburner Manager not found
- Error registering server(s)
- Error writing output file
- Loading time-outs

**Warning** — Non-fatal warning information. These are events that do not cause the application to stop rendering a job. These messages are preceded by a brown “WRN” label, and include the following events:

- Backburner Manager or Backburner Servers shutting down
- Server(s) flagged as failed
- Loading time-out set too low
- Rendering time-out set too low

**Info** — General information about the current status of Backburner Manager and the Backburner Servers on the Backburner network. These messages are preceded by an aqua “INF” label, and include the following events:

- Booting Backburner Manager
- Connection to Backburner Server(s)
- Registration to Backburner Manager
- Job submitted
- Job received

- Frame complete

**Debug and Debug Extended** — Detailed information about TCP/IP packets and the current state of Backburner Manager and the Backburner Servers. Debug Extended provides a more verbose listing than Debug. These messages are preceded by a blue “DBG” label, and include the following information:

- TCP/IP packets sent and received
- TCP/IP packet collection
- Frames assigned
- Log files creation and sending
- Assignment threads

## Editing the *backburner.xml* File

When you run the Backburner Manager or Server, the application creates or updates the *backburner.xml* file in the Network directory under the Backburner installation directory. View or edit this file only if you have isolated a particular workstation as the cause of problems experienced on the Backburner network.

You may change parameters in the *backburner.xml* file by editing it in an XML editor or a text editing application.

On Windows systems, most of the settings in the *backburner.xml* file can be set using the Manager Properties dialog and Server Properties dialog.

Before viewing or editing the *backburner.xml* file, make sure the Backburner Manager and/or Backburner Server applications are shut down (or their services stopped and uninstalled). Any changes made to the *backburner.xml* file take effect only when the Backburner Manager or Server is restarted.

**NOTE:** Changing parameters manually in the *backburner.xml* file is done at your own risk.

Autodesk recommends changing only the following parameters in this file:

**MaxBlockSize** — Located under the <GeneralCfg> heading, this value is the maximum size of a data packet sent when transferring large blocks, such as projects. For slow connections like modems, use a smaller packet size, for example, 1024.

**NetworkMask** — Located under the <GeneralCfg> heading, this value shows the subnet mask used to locate other Backburner network components, such as Backburner Server or Manager. The subnet mask defined in the *backburner.xml* file must be the same as the one defined for general TCP/IP communications on the workstation.

**ServerName** — Located under the <SystemConfiguration><AppDetails><ServerSettings> heading, this value specifies either the host name or IP address the Backburner Server uses to identify itself to the Backburner Manager. This is useful when a render node has more than one network interface and hence more than one IP address

**Acknowledgment Timeout** — Located under the <TimerCfg> heading as AckTimeout, this value is the amount of time (in seconds) that the system waits for an acknowledgment of commands (like Ping) sent back and forth between the Manager and Server. The default acknowledgment timeout is 20 seconds.

**Acknowledgment Retries** — Located under the <TimerCfg> heading as AckRetries, this value determines how many times the sender retries if no acknowledgment is received. The default is six tries. After that, the machine is considered down and is put off-line.

## Resolving a Host Access Error

The common causes of a host access error in Linux or Windows installations are an incorrect IP address for the Backburner Manager, incorrect port numbers for the Manager and/or Server, or incorrectly configured TCP/IP information. You can troubleshoot the error by examining each of these in turn.

### To resolve a host access error:

1. Ensure that the name and IP address of the Backburner Manager are correctly specified in the Backburner Server, as follows.

Connect the application directly to the Backburner Manager workstation by trying the following:

- If you use the Auto-Connect functionality, disable the Use First Available option and/or remove the subnet mask for the Backburner network. You are prompted to enter the name or IP address of the Backburner Manager workstation when you try to submit a job to Backburner.
- Disable any settings or preferences that automatically connect to the Backburner Manager.

If the application cannot connect to the Backburner Manager, continue to the next step.

2. Verify that the Manager and Server port numbers are correctly specified in the Manager General Properties and Server General Properties.

If this does not solve the problem, continue to the next step.

3. Verify that TCP/IP is correctly configured on all workstations running the software. If necessary, verify that the subnet mask is correct.

**NOTE:** Consult your network administrator before changing the subnet mask.

4. If a firewall is running on Backburner components, review the firewall settings for each network component to ensure the following:
  - The Backburner application(s) are allowed to access the network.
  - The ports used by the Backburner Manager and the Backburner Monitor to communicate are not blocked by the firewall. By default, these ports are 3233 and 3234.

## Resolving Invalid DNS Addresses

An invalid Domain Name Server (DNS) address in the DNS Search Order, or in the Primary or Secondary WINS Server in the Microsoft Windows TCP/IP dialog, causes an `Error registering <server name>` error when you start Backburner Manager or Server. The following procedure describes how to resolve invalid IP addresses for the Domain Name Server.

### To resolve invalid DNS addresses:

1. Display the Microsoft TCP/IP dialog.  
In Windows XP, from the Start menu, choose Settings, then Network Connections. Next, right-click Local Area Connection, and then click Properties. In the list, select Internet Protocol (TCP/IP) and click Properties. In the dialog that appears, click Use the following DNS server addresses, click Advanced and then check the DNS and WINS tabs.
2. Check the IP addresses listed for DNS and WINS servers for invalid IP addresses. If there are invalid IP Addresses listed in either the DNS or WINS Address panel, correct them and then reboot the workstation.

## Resolving a Problem Connecting to the Backburner Manager

The Backburner Manager, on Linux or Windows systems, is the link between the Render Clients who submit jobs and the render nodes that process these jobs. If the Backburner Manager is not available, jobs cannot be submitted to or processed by Backburner. Not being able to connect to the Backburner Manager causes problems for both Render Clients and nodes, but Render Clients usually discover the problem. For example, if you submit a job while the Manager is down, an error appears in your application.



The most common reasons for not being able to connect to the Backburner Manager are:

- An incorrect IP address or an IP address that connects to the wrong Backburner Manager
- A Backburner Manager that is not running or is hung
- Communication problems between the Backburner Manager and the render nodes

**To resolve a problem connecting to the Backburner Manager:**

1. Ensure you are connecting to the correct Backburner Manager, using its correct IP address, as follows.

Connect the application directly to the Backburner Manager workstation by trying the following:

- If you use the Auto-Connect functionality, disable the Use First Available option and/or remove the subnet mask for the Backburner network. You are prompted to enter the name or IP address of the Backburner Manager workstation when you try to submit a job to the Backburner.
- Disable any settings or preferences that automatically connect to the Backburner Manager.

If the application cannot connect to the Backburner Manager, continue to the next step.

2. Verify that the Backburner Manager is running.

If it is not running or appears to be inactive on the workstation, restart the Manager for the network. Refer to the *Autodesk Backburner Installation Guide* for help starting Backburner Manager.

**NOTE:** If you are running Backburner Manager as a Windows Service, display the Services control panel, and verify that the Manager service is running. If the service is not running, highlight it and click Start.

If restarting the Manager does not fix the problem, continue to the next step.

3. If a render node has more than one network interface, these problem may be that the Backburner Server running on that node is identifying itself to the Backburner Manager using the wrong IP address. Do one of the following on the node to specify the IP address the Backburner Server uses to identify itself to the Backburner Manager:
  - (Windows render node) Stop the Backburner Server on the node, and the Backburner Manager. On the render node, from the Start menu, choose Programs, Autodesk, Backburner, then server to open the Backburner Server General Properties dialog and in

the Server Name or IP Address field, enter the name or IP address you want to associate with the Backburner Server. Restart the Backburner Manager and the Backburner Server.

- (Windows or Linux render node) Stop the Backburner Server on the node, and the Backburner Manager. Load the `/usr/discreet/backburner/Network/backburner.xml` file in an XML editor or text editor and edit the `<SystemConfiguration>/<AppDetails>/<ServerSettings>/<ServerName>` values to reflect the host name or IP address you want to associate with the Backburner Server. Save and close the file, then restart the Backburner Manager and the Backburner Server.

4. Ensure the render nodes can *ping* the Backburner Manager. For help with the *ping* command, see [“Verifying Communication Between Two Hosts”](#) on page 91.  
If the render nodes can successfully *ping* the Backburner Manager, continue to the next step.
5. If a firewall is running on Backburner components, review the firewall settings for each network component to ensure the following:
  - The Backburner application(s) are allowed to access the network.
  - The ports used by the Backburner Manager and the Backburner Monitor to communicate are not blocked by the firewall. By default, these ports are 3233 and 3234.
6. Configure the log files to report detailed information about TCP/IP packets, as follows.  
Enable the Log Debug and Log Debug Extended options in the preferences for the Manager and all render nodes running Backburner Server, and then restart the Backburner Manager and Backburner Server workstations.  
  
Examine the TCP/IP information in the log files to determine why the Backburner Manager workstation and render nodes are not communicating.
7. Examine the *backburner.xml* file to ensure that the subnet mask defined for the Backburner Manager is correct and matches the subnet mask defined for the render node’s TCP/IP settings. See [“Editing the backburner.xml File”](#) on page 96.

## Adding the Backburner Path to the Windows Path Environment Variable

Environment variables are file paths that help Microsoft Windows find and launch applications such as Backburner Server. If the path to Backburner is missing or incorrectly

defined, Windows is not able to launch Backburner Server or the application associated with the job. When this happens, the following errors may appear in the following applications:

- Unknown error loading application in the Backburner Manager and the Backburner Monitor.
- Cannot Network Render. Backburner not found or not installed. in the application that submitted the job to the Backburner network.

Do the following procedure to add Backburner to the *Path* environment variable in Windows.

**To add the Backburner path to the Windows path environment variable:**

1. In Windows XP, from the Start menu, choose Settings, Control Panel, then System. The System Properties dialog appears.
2. Show the Advanced tab, and then click Environment Variables to display the environment variables.  
The Environment Variables dialog appears, showing user and system environment variables defined for the Windows workstation.
3. From the System Variables list, choose Path and then click Edit.  
The contents of the *Path* environment variable appear.
4. Check the *Path* environment variable for the file path to Backburner: *C:\Program Files\Autodesk\Backburner\* (default). If this path is missing or is incorrectly specified, re-enter it.
5. Click OK to return to the Environment Variables dialog, then close all dialogs and restart the Windows workstation.

## Resolving Network Card Priority

If you have multiple network cards in your Linux or Windows render node, by default, Backburner Server uses the IP address of the first network card that it finds to identify itself to the Backburner Manager. This may lead to problems if this is the wrong card. You can force Backburner Server to use a specific network card. The following procedure describes how.

**To resolve network card priority:**

- Do one of the following:
  - (Windows render node) Stop the Backburner Server on the node, and the Backburner Manager. Then on the render node, from the Start menu, choose Programs, Autodesk, Backburner, then server to open the Backburner Server General Properties dialog and in

the Server Name or IP Address field, enter the name or IP address you want to associate with the Backburner Server. Restart the Backburner Manager and the Backburner Server.

- (Windows or Linux render node) Stop the Backburner Server on the node, and the Backburner Manager. Load the `/usr/discreet/backburner/Network/backburner.xml` file in an XML editor or text editor and edit the `<SystemConfiguration>/<AppDetails>/<ServerSettings>/<ServerName>` to reflect the host name or IP address you want to associate with the Backburner Server. Save and exit the file, then restart the Backburner Manager and the Backburner Server.

## Resolving an Unavailable Render Node Problem

The most common reasons, in a Linux or Windows system, that a render node appears unavailable are that the workstation is offline, the Backburner Server is not running or is hung, the Server is not using the correct IP address for the Manager, or the Manager cannot communicate with the Server.

### To resolve an unavailable render node problem:

1. Verify that the render node workstation is online.

If you are not at the render node, use the `ping` command to see this workstation is online.

For help with the `ping` command, see [“Verifying Communication Between Two Hosts”](#) on page 91.

If the workstation is not online, restart the render node, and then see if it appears in the Backburner network.

If this does not resolve the problem, continue to the next step.

2. Check if the render node is scheduled to be offline using the Windows-based Backburner Monitor. See [“Setting Render Node Availability”](#) on page 48.

If the render node is scheduled to be offline and it should be online at this time, change the schedule for the render node.

If this does not resolve the problem, continue to the next step.

3. Verify the Backburner Server is running.

If it is not running or is hung, start the Server. Refer to the *Autodesk Backburner Installation Guide* for help starting Backburner Server.

**NOTE:** If you are running Backburner Server as a Windows Service, display the Services control panel, and verify that the Server service is running. If the service is not running, highlight it and click Start.

If this does not fix the problem, continue to the next step.

4. For Windows systems only, verify that the render node can communicate with the correct Manager.

Connect the render node directly to the Backburner Manager workstation by doing the following:

- Disable any Backburner Server settings or preferences that automatically connect to the Backburner Manager. In the Backburner Server General Properties dialog, disable Automatic Search and manually enter the name or IP address of the Backburner Manager.
- If the render node has more than one network card, in the Backburner Server General Properties dialog, manually enter the name or IP address you want to assign to the Backburner Server in the Server Name or IP Address field.
- Verify that the *HOSTS* file located in the *winnt\system32\drivers\etc\* directory includes the IP address and corresponding machine name for each render node and the Backburner Manager workstation on the network. This file maps machine names to IP addresses.

If restarting the Server after this step does not fix the problem, continue to the next step.

5. If a firewall is running on Backburner network components, review the firewall settings for each network component to ensure the following:
  - The Backburner application(s) are allowed to access the network.
  - The ports used by the Backburner Manager and the Backburner Monitor to communicate are not blocked by the firewall. By default, these ports are 3233 and 3234.
6. Verify that the Manager can *ping* the render node. See [“Verifying Communication Between Two Hosts”](#) on page 91.

If the Manager can successfully *ping* the render node, continue to the next step.

7. Configure the log files to report detailed information about TCP/IP packets, as follows. Enable the Log Debug and Log Debug Extended options in the preferences for the Backburner Manager and the Backburner Server workstations, and then restart the Backburner Manager and Backburner Server applications.

Examine the TCP/IP information in the log files to determine why the render node and Backburner Manager are not communicating.

## Restarting Suspended Render Nodes

If the Backburner Monitor or the Backburner Web Monitor indicates that a render node assigned to a job is suspended even if its job is being processed, do the following to determine why the render node is suspended and, if necessary, to restart it.

### To determine the cause of, and restart, a suspended render node:

1. Before restarting the render node, make sure that the workstation is available to render jobs. Select the render node in the Server List to view its details. Check in the Schedule section to see if the node is disabled for the current time period.

Render nodes that are not set to be available for rendering may appear suspended even if their job is being processed.

2. If the render node is supposed to be available for rendering jobs, stop and restart the Backburner Server application on the render node.

## Resolving a Render Node Failure

The following list shows possible causes to verify in the case of a render node failure. Most of these are logged in the *backburnerServer.log* file, if you have configured the log file to include fatal errors. Consulting this log file may help you determine the reason for the render node failure.

- Verify the paths to the footage and to the output folder are valid from the render node. A render node may fail if it cannot access the footage for a job, or cannot save its output in the output folder. Where possible, use UNC (*\\machine\folder*) paths for footage, such as bitmaps used for textures in 3D models. You can also ensure that paths to footage and projects are identical by maintaining the same directory structure on all Render Clients and render nodes in the Backburner network.
- Verify that any plug-ins, fonts, and codecs necessary for rendering jobs are installed on the render node.
- Ensure there is sufficient disk space to accommodate output (on the drive to which the render node saves its output), as well to hold input data associated with jobs (on the local drive of the render node).

## Adjusting the Maximum Number of Render Nodes Per Job

When the maximum number of render nodes per job is reached, no additional render nodes can be assigned to a job, even if render nodes are available. You can remedy this problem by adjusting the settings for the Maximum Concurrent Assignments and Maximum Servers per

Job in Backburner Manager. You can do this by editing the *backburner.xml* file. Additionally, on Windows systems you can use the Backburner Manager General Properties dialog.

**NOTE:** Changing these settings is not recommended. Increase these values only if you are sure that there is sufficient slack in your Backburner network.

**To adjust the number of render nodes per job on Windows systems:**

1. In Backburner Manager, from the Edit menu, choose General Settings.

The Backburner Manager General Properties dialog appears.

The screenshot shows the 'Backburner Manager General Properties' dialog box. It is divided into several sections. The 'TCP/IP' section has 'Manager Port' set to 3234 and 'Server Port' set to 3233. The 'Failed Servers' section has 'Restart Failed Servers' checked, 'Number of Retries' set to 3, and 'Seconds Between Retries' set to 30. The 'Direct Access to Jobs Path' section has 'Use Jobs Path' unchecked, with empty fields for 'Win32 Path' and 'Unix Path'. The 'Default Job Handling' section has 'Do Nothing' selected as the action after a job is successfully completed. There are also options for 'Delete it' and 'Archive it', with 'Delete After' set to 7 days and 'Archive After' set to 4 days. At the bottom of the dialog are 'OK' and 'Cancel' buttons.

**NOTE:** Changing these settings is not recommended. Increase these values only if you are sure that there is sufficient slack in your Backburner network.

2. In the General group, adjust the value for Max Concurrent Assignments.
3. Optionally, in the General group, select Use Server Limit and adjust the value for Max Servers per Job.

**NOTE:** The settings from the Backburner Manager General Properties dialog are also written to the *backburner.xml* file in the *Network* folder where you installed Backburner.

**To adjust the number of render nodes by editing the *backburner.xml* file:**

1. Stop Backburner Manager.
  2. Locate the *backburner.xml* file:
    - Linux: */usr/discreet/backburner/Network*
    - In the *\backburner* subdirectory of the per-user application data directory. For example, *C:\Documents and Settings\<user>\Local Settings\Application Data\backburner*, in Windows XP.
  3. Edit the *backburner.xml* file using an XML or text editing application.
  4. Under `<ManagerSettings>`, adjust the value for `<MaxConcurrentAssignments>`.
  5. Optionally, set `<UseServerLimit>` to “Yes”, and adjust the value for `<ServerLimit>`.
- NOTE:** Changing these settings is not recommended. Increase these values only if you are sure that there is sufficient slack in your Backburner network.
6. Save and exit the *backburner.xml* file.
  7. Restart Backburner Manager. Refer to the *Autodesk Backburner Installation Guide* for help starting Backburner Manager.

**NOTE:** Any changes made to the *backburner.xml* file take effect only when the Backburner Manager is restarted.

The new render node settings take effect.



# index

## Numerics

### 3ds Max

- cloning jobs 23
- render nodes 24, 25, 47, 72

## B

### Backburner

- architecture 6
- defined 3
- log files 105
- supported applications 3
- terminology 4
- Windows environment variables 100

### Backburner Manager

- defined 6
- log files 92, 105
- problem connecting to 98

### Backburner Monitor

- comparing 10
- defined 6
- getting started 9
- see also Backburner Web Monitor
- see also Backburner Windows Monitor

### Backburner Server

- defined 7
- log files 92, 105
- see also render nodes

### Backburner Web Monitor

- "Read Only" in title bar 14
- defined 10
- launching 16
- queue control 16

### Backburner Windows Monitor

- defined 10

### launching 11

### queue control 14

### Backburner WiretapCentral Monitor

### see WiretapCentral Backburner Monitor

### backburner.xml file 96

### bucket rendering 5

## C

### Cleaner XL

### assigning render nodes 25

### cloning jobs 23

### command line rendering 82, 83

### customer support 7

## D

### documentation 7

## J

### jobs

### archiving 23, 39, 65

### assigning render nodes to 22, 47, 72

### cloning 23, 38, 63

### deleting 23, 40, 67

### modifying settings 22, 35, 60

### monitoring 21, 32, 55

### overview 21

### restarting 22, 38, 63

### restarting vs reactivating 22

### submitting from command line 82, 83

### suspending and reactivating 21, 34, 59

### viewing status 21, 32, 55

## L

log files 92, 105

## M

multiple network cards 101

## P

packets

defined 5

verifying packet size 92

*ping* command 91

## Q

queue control

and administrator privileges 11

Backburner Web Monitor 16

Backburner Windows Monitor 11, 12

obtaining 14

## R

render nodes

and Cleaner XL jobs 25

and Wire transfer jobs 25

assigning to jobs 24, 47, 72

creating server groups 26, 49, 76

defined 7

deleting absent/offline 25, 48, 74

"ghost" nodes 25

monitoring 24, 44, 69

overview 24

restarting 104

scheduling availability 25, 48, 75

setting max. nodes per job 104

## S

server groups

and job processing strategies 26

creating 26, 49, 76

defined 26

global server groups 50

local server groups (3ds Max) 49

## T

troubleshooting

basic techniques 87

host access errors 97

invalid DNS addresses 98

job submission 89

render node failure 104

render nodes 90

startup problems 88

unavailable render node 102

verifying communication 91

## V

Visual Effects and Finishing applications

cloning jobs 23

submitting jobs to server groups 26, 50, 76

## W

Wire transfers

assigning render nodes 25

WiretapCentral Backburner Monitor

launching 20

overview 19